

ChemicalProcess

Totally Integrated Automation Portal																																																																																																																																								
Table of contents ChemicalProcess <table><tr><td>PLC_1 [CPU 1511-1 PN]</td><td>4 - 1</td></tr><tr><td>Software units</td><td>5 - 1</td></tr><tr><td>Program blocks</td><td></td></tr><tr><td> Main [OB1]</td><td>6 - 1</td></tr><tr><td> ProcessSequence [FB1]</td><td>7 - 1</td></tr><tr><td> ProcessSequence_DB [DB3]</td><td>8 - 1</td></tr><tr><td> FB_TestMode [FB9]</td><td>9 - 1</td></tr><tr><td> DB_TestMode [DB24]</td><td>10 - 1</td></tr><tr><td>System blocks</td><td></td></tr><tr><td> Program resources</td><td></td></tr><tr><td> MixTankMotorTimer [DB2]</td><td>11 - 1</td></tr><tr><td> Motors</td><td></td></tr><tr><td> Generic Motors</td><td></td></tr><tr><td> FC_Motor_Set [FC5]</td><td>12 - 1</td></tr><tr><td> FC_Motor_Reset [FC6]</td><td>13 - 1</td></tr><tr><td> FB_Motor [FB11]</td><td>14 - 1</td></tr><tr><td> Data Blocks</td><td></td></tr><tr><td> DB_M001 [DB10]</td><td>15 - 1</td></tr><tr><td> DB_M002 [DB14]</td><td>16 - 1</td></tr><tr><td> DB_M003 [DB18]</td><td>17 - 1</td></tr><tr><td> Sensors</td><td></td></tr><tr><td> Generic Blocks</td><td></td></tr><tr><td> FC_Scale [FC2]</td><td>18 - 1</td></tr><tr><td> SensorScaling [FB3]</td><td>19 - 1</td></tr><tr><td> DataBlocks</td><td></td></tr><tr><td> DB_Sensor_LI_515 [DB15]</td><td>20 - 1</td></tr><tr><td> Db_Sensor_TI_517 [DB16]</td><td>21 - 1</td></tr><tr><td> DB_Sensor_TI_518 [DB17]</td><td>22 - 1</td></tr><tr><td> DB_Sensor_WI_512 [DB12]</td><td>23 - 1</td></tr><tr><td> DB_Sensor_FIC_516 [DB4]</td><td>24 - 1</td></tr><tr><td> Valves</td><td></td></tr><tr><td> Generic valves</td><td></td></tr><tr><td> Valves [FC1]</td><td>25 - 1</td></tr><tr><td> FB_Valve [FB2]</td><td>26 - 1</td></tr><tr><td> DataBlock_Valves</td><td></td></tr><tr><td> DB_GSV_510 [DB5]</td><td>27 - 1</td></tr><tr><td> DB_GSV_511 [DB6]</td><td>28 - 1</td></tr><tr><td> DB_GSV_514 [DB7]</td><td>29 - 1</td></tr><tr><td> DB_GSV_519 [DB8]</td><td>30 - 1</td></tr><tr><td> DB_GSV_521 [DB9]</td><td>31 - 1</td></tr><tr><td> Process</td><td></td></tr><tr><td> Data Blocks</td><td></td></tr><tr><td> DB_HMI [DB19]</td><td>32 - 1</td></tr><tr><td> DB_AutoMode [DB20]</td><td>33 - 1</td></tr><tr><td> DB_Fault [DB23]</td><td>34 - 1</td></tr><tr><td> DB_ManualMode [DB21]</td><td>35 - 1</td></tr><tr><td> DB_Stop [DB22]</td><td>36 - 1</td></tr><tr><td> Process FBs</td><td></td></tr><tr><td> FB_HMI [FB8]</td><td>37 - 1</td></tr><tr><td> FB_Auto [FB4]</td><td>38 - 1</td></tr><tr><td> FB_EStop [FB6]</td><td>39 - 1</td></tr><tr><td> FB_Fault [FB7]</td><td>40 - 1</td></tr><tr><td> FB_Manual [FB5]</td><td>41 - 1</td></tr><tr><td> Technology objects</td><td></td></tr><tr><td> DB_PID_Compact [DB11]</td><td>42 - 1</td></tr><tr><td> PID_Compact_1 [DB1]</td><td>43 - 1</td></tr><tr><td> PID_M003 [DB13]</td><td>44 - 1</td></tr><tr><td> PLC tags</td><td></td></tr><tr><td> Default tag table [55]</td><td></td></tr><tr><td> PLC tags</td><td>45 - 1</td></tr><tr><td> User constants</td><td>46 - 1</td></tr><tr><td> SIMIT interface [34]</td><td></td></tr><tr><td> PLC tags</td><td>47 - 1</td></tr><tr><td> User constants</td><td>48 - 1</td></tr><tr><td> PLC data types</td><td></td></tr><tr><td> System data types</td><td>49 - 1</td></tr></table>			PLC_1 [CPU 1511-1 PN]	4 - 1	Software units	5 - 1	Program blocks		Main [OB1]	6 - 1	ProcessSequence [FB1]	7 - 1	ProcessSequence_DB [DB3]	8 - 1	FB_TestMode [FB9]	9 - 1	DB_TestMode [DB24]	10 - 1	System blocks		Program resources		MixTankMotorTimer [DB2]	11 - 1	Motors		Generic Motors		FC_Motor_Set [FC5]	12 - 1	FC_Motor_Reset [FC6]	13 - 1	FB_Motor [FB11]	14 - 1	Data Blocks		DB_M001 [DB10]	15 - 1	DB_M002 [DB14]	16 - 1	DB_M003 [DB18]	17 - 1	Sensors		Generic Blocks		FC_Scale [FC2]	18 - 1	SensorScaling [FB3]	19 - 1	DataBlocks		DB_Sensor_LI_515 [DB15]	20 - 1	Db_Sensor_TI_517 [DB16]	21 - 1	DB_Sensor_TI_518 [DB17]	22 - 1	DB_Sensor_WI_512 [DB12]	23 - 1	DB_Sensor_FIC_516 [DB4]	24 - 1	Valves		Generic valves		Valves [FC1]	25 - 1	FB_Valve [FB2]	26 - 1	DataBlock_Valves		DB_GSV_510 [DB5]	27 - 1	DB_GSV_511 [DB6]	28 - 1	DB_GSV_514 [DB7]	29 - 1	DB_GSV_519 [DB8]	30 - 1	DB_GSV_521 [DB9]	31 - 1	Process		Data Blocks		DB_HMI [DB19]	32 - 1	DB_AutoMode [DB20]	33 - 1	DB_Fault [DB23]	34 - 1	DB_ManualMode [DB21]	35 - 1	DB_Stop [DB22]	36 - 1	Process FBs		FB_HMI [FB8]	37 - 1	FB_Auto [FB4]	38 - 1	FB_EStop [FB6]	39 - 1	FB_Fault [FB7]	40 - 1	FB_Manual [FB5]	41 - 1	Technology objects		DB_PID_Compact [DB11]	42 - 1	PID_Compact_1 [DB1]	43 - 1	PID_M003 [DB13]	44 - 1	PLC tags		Default tag table [55]		PLC tags	45 - 1	User constants	46 - 1	SIMIT interface [34]		PLC tags	47 - 1	User constants	48 - 1	PLC data types		System data types	49 - 1		
PLC_1 [CPU 1511-1 PN]	4 - 1																																																																																																																																							
Software units	5 - 1																																																																																																																																							
Program blocks																																																																																																																																								
Main [OB1]	6 - 1																																																																																																																																							
ProcessSequence [FB1]	7 - 1																																																																																																																																							
ProcessSequence_DB [DB3]	8 - 1																																																																																																																																							
FB_TestMode [FB9]	9 - 1																																																																																																																																							
DB_TestMode [DB24]	10 - 1																																																																																																																																							
System blocks																																																																																																																																								
Program resources																																																																																																																																								
MixTankMotorTimer [DB2]	11 - 1																																																																																																																																							
Motors																																																																																																																																								
Generic Motors																																																																																																																																								
FC_Motor_Set [FC5]	12 - 1																																																																																																																																							
FC_Motor_Reset [FC6]	13 - 1																																																																																																																																							
FB_Motor [FB11]	14 - 1																																																																																																																																							
Data Blocks																																																																																																																																								
DB_M001 [DB10]	15 - 1																																																																																																																																							
DB_M002 [DB14]	16 - 1																																																																																																																																							
DB_M003 [DB18]	17 - 1																																																																																																																																							
Sensors																																																																																																																																								
Generic Blocks																																																																																																																																								
FC_Scale [FC2]	18 - 1																																																																																																																																							
SensorScaling [FB3]	19 - 1																																																																																																																																							
DataBlocks																																																																																																																																								
DB_Sensor_LI_515 [DB15]	20 - 1																																																																																																																																							
Db_Sensor_TI_517 [DB16]	21 - 1																																																																																																																																							
DB_Sensor_TI_518 [DB17]	22 - 1																																																																																																																																							
DB_Sensor_WI_512 [DB12]	23 - 1																																																																																																																																							
DB_Sensor_FIC_516 [DB4]	24 - 1																																																																																																																																							
Valves																																																																																																																																								
Generic valves																																																																																																																																								
Valves [FC1]	25 - 1																																																																																																																																							
FB_Valve [FB2]	26 - 1																																																																																																																																							
DataBlock_Valves																																																																																																																																								
DB_GSV_510 [DB5]	27 - 1																																																																																																																																							
DB_GSV_511 [DB6]	28 - 1																																																																																																																																							
DB_GSV_514 [DB7]	29 - 1																																																																																																																																							
DB_GSV_519 [DB8]	30 - 1																																																																																																																																							
DB_GSV_521 [DB9]	31 - 1																																																																																																																																							
Process																																																																																																																																								
Data Blocks																																																																																																																																								
DB_HMI [DB19]	32 - 1																																																																																																																																							
DB_AutoMode [DB20]	33 - 1																																																																																																																																							
DB_Fault [DB23]	34 - 1																																																																																																																																							
DB_ManualMode [DB21]	35 - 1																																																																																																																																							
DB_Stop [DB22]	36 - 1																																																																																																																																							
Process FBs																																																																																																																																								
FB_HMI [FB8]	37 - 1																																																																																																																																							
FB_Auto [FB4]	38 - 1																																																																																																																																							
FB_EStop [FB6]	39 - 1																																																																																																																																							
FB_Fault [FB7]	40 - 1																																																																																																																																							
FB_Manual [FB5]	41 - 1																																																																																																																																							
Technology objects																																																																																																																																								
DB_PID_Compact [DB11]	42 - 1																																																																																																																																							
PID_Compact_1 [DB1]	43 - 1																																																																																																																																							
PID_M003 [DB13]	44 - 1																																																																																																																																							
PLC tags																																																																																																																																								
Default tag table [55]																																																																																																																																								
PLC tags	45 - 1																																																																																																																																							
User constants	46 - 1																																																																																																																																							
SIMIT interface [34]																																																																																																																																								
PLC tags	47 - 1																																																																																																																																							
User constants	48 - 1																																																																																																																																							
PLC data types																																																																																																																																								
System data types	49 - 1																																																																																																																																							

Totally Integrated Automation Portal		
Watch and force tables		
Force table		50 - 1
Traces		51 - 1
Measurements		52 - 1
Combined measurements		53 - 1
OPC UA communication		
Server interfaces		54 - 1
Client interfaces		55 - 1
PLC supervisions & alarms		
Supervisions		56 - 1
PLC alarms		57 - 1
System alarms		58 - 1
PLC alarm text lists		59 - 1
Local modules		
PS 25W 24VDC_1		60 - 1
PLC_1 [CPU 1511-1 PN]		61 - 1
DI 16x24VDC BA_1		62 - 1
DQ 16x24VDC/0.5A BA_1		63 - 1
AI 8xU/I/RTD/TC ST_1		64 - 1
AQ 2xU/I ST_1		65 - 1
DI 16x24VDC BA_2		66 - 1
HMI_1 [KTP700 Basic PN]		67 - 1
Runtime settings		68 - 1
Screens		
Different jobs		69 - 1
Project information		70 - 1
Root screen		71 - 1
SIMATIC PLC system diagnostics		72 - 1
System information		73 - 1
System screens		74 - 1
User administration		75 - 1
Screen management		
Templates		
Template_1		76 - 1
Global screen		77 - 1
HMI tags		
Default tag table [17]		78 - 1
Connections		79 - 1
HMI alarms		
Discrete alarms		80 - 1
Analog alarms		81 - 1
Alarm groups		82 - 1
Alarm classes		83 - 1
System events		84 - 1
Recipes		85 - 1
Historical data		
Datalogs		86 - 1
AlarmLogs		87 - 1
Scheduled tasks		88 - 1
Text and graphic lists		
Text lists		89 - 1
Graphic lists		90 - 1
User administration		
User		91 - 1
Groups		92 - 1
Authorizations		93 - 1
Ungrouped devices		94 - 1
Security settings		95 - 1
Cross-device functions		
Project traces		
Measurements		96 - 1
Common data		
Alarm classes		97 - 1
Logs		98 - 1
Styles		99 - 1
Languages & resources		
Project languages		100 - 1
Project texts		
Project texts		101 - 1

Totally Integrated Automation Portal		
Project graphics		102 - 1

Totally Integrated Automation Portal							
ChemicalProcess							
Project							
Name:	ChemicalProcess	Creation time:	5/25/2021 7:32:50 AM	Last change	5/10/2026 3:31:40 PM	Author:	mika3
Last modified by:	amk1008619	Version:					
Comment:							
Operating system							
Name				Description			
Operating system				Microsoft Windows 11 Enterprise			
Version of the operating system				6.3.9600.0			
Operating system service pack							
Version of the Internet Explorer				11.1882.26100.0			
Computer name				avd-vlk-001			
User name				HAMK\amk1008619			
Installation path of the TIA Portal				C:\Program Files\Siemens\Automation\Portal V16			
Components							
Name			Version		Release		
TIA Portal Project Server V16 - TIA Portal Project Server Single SetupPackage V16.0 Upd5 (MUSERVERV16)			V16.0 + Upd5		V16.00.00.05_04.01.00.01		
SIMATIC S7-PLCSIM (S7_PLCSIM_V16)			V16.0		V16.00.00.00_31.02.00.01		
Siemens Totally Integrated Automation Portal V16 - SIMATIC S7-PLCSIM V16.0 + SP0 + Upd4 (S7_PLCSIM_V16)			V16.0 + SP0 + Upd4		V16.00.00.04_01.00.04.01		
TIA Administrator - AWB Licensing Module V1.0 + SP8 (TIAADMIN)			V1.0 + SP8		V01.00.08.00_01.01.00.18		
TIA Administrator - AWB Software Management V1.0 + SP8 (TIAADMIN)			V1.0 + SP8		V01.00.08.00_01.01.00.18		
TIA Administrator - TIA UMC Agent Configurator Module V1.0 + SP8 (TIAADMIN)			V1.0 + SP8		V01.00.08.00_01.01.00.18		
TIA Administrator - TIA Administrator V1.0 SP8 (TIAADMIN)			V1.0 + SP8		V01.00.08.00_01.01.00.18		
Totally Integrated Automation Portal V16 - TIA Portal Single SetupPackage V16.0 (TIAP16)			V16.0 UPD8		V16.00.00.08_05.01.00.01		
Siemens Totally Integrated Automation Portal V16 - HM All Editions Single SetupPackage V16.0 UPD8 (TIAP16)			V16.0 UPD8		V16.00.00.08_05.01.00.01		
Siemens Totally Integrated Automation Portal V16 - HM NoBasic Single SetupPackage V16.0 UPD8 (TIAP16)			V16.0 UPD8		V16.00.00.08_05.01.00.01		
Siemens Totally Integrated Automation Portal V16 - Hardware Support Base Package 0 V16.0 (TIAP16)			V16.0		V16.00.00.00_27.01.00.01		
Siemens Totally Integrated Automation Portal V16 - Multiuser Client Single SetupPackage V16.0 UPD8 (TIAP16)			V16.0 UPD8		V16.00.00.08_05.01.00.01		
Siemens Totally Integrated Automation Portal V16 - Version Control Interface SetupPackage V16.0 UPD8 (TIAP16)			V16.0 UPD8		V16.00.00.08_05.01.00.01		
Siemens Totally Integrated Automation Portal V16 - STEP 7 Safety Single SetupPackage V16.0 UPD7 (TIAP16)			V16.0 UPD7		V16.00.00.07_04.01.00.02		
Siemens Totally Integrated Automation Portal V16 - SINAMICS Startdrive G110M, G120, G120C, G120D, G120P, G115D V16.0 + Upd5 (TIAP16)			V16.0 + Upd5		V16.00.00.05_20.09.00.07		
Siemens Totally Integrated Automation Portal V16 - Startdrive Hardware Support Base Package 1 V16.0 (TIAP16)			V16.0		V16.00.00.00_20.00.00.04		
Siemens Totally Integrated Automation Portal V16 - SINAMICS-STARTDRIVE-COMMON V16.0 + Upd5 (TIAP16)			V16.0 + Upd5		V16.00.00.05_20.09.00.07		
Siemens Totally Integrated Automation Portal V16 - SINAMICS-STARTDRIVE-COMMON-OPENNESS V16.0 + Upd5 (TIAP16)			V16.0 + Upd5		V16.00.00.05_20.09.00.07		
Siemens Totally Integrated Automation Portal V16 - SINAMICS-STARTDRIVE-COMMON-SAT V16.0 + Upd5 (TIAP16)			V16.0 + Upd5		V16.00.00.05_20.09.00.07		
Siemens Totally Integrated Automation Portal V16 - SINAMICS Startdrive G130, G150, S120, S150, SINAMICS MV V16.0 + Upd5 (TIAP16)			V16.0 + Upd5		V16.00.00.05_20.09.00.07		
Siemens Totally Integrated Automation Portal V16 - STEP 7 Single SetupPackage V16.0 UPD8 (TIAP16)			V16.0 UPD8		V16.00.00.08_05.01.00.01		
Siemens Totally Integrated Automation Portal V16 - Hardware Support Base Package 02 V16.0 (TIAP16)			V16.0		V16.00.00.00_27.01.00.01		
Siemens Totally Integrated Automation Portal V16 - Hardware Support Base Package 03 V16.0 (TIAP16)			V16.0		V16.00.00.00_27.01.00.01		
Siemens Totally Integrated Automation Portal V16 - Hardware Support Base Package 04 V16.0 (TIAP16)			V16.0		V16.00.00.00_27.01.00.01		
Siemens Totally Integrated Automation Portal V16 - Support Base Package TO-01 V16.0 (TIAP16)			V16.0		V16.00.00.00_27.01.00.01		
Siemens Totally Integrated Automation Portal V16 - Support Base Package TO-02 V16.0 (TIAP16)			V16.0		V16.00.00.00_27.01.00.01		
Siemens Totally Integrated Automation Portal V16 - Hardware Support Base Package WCF-01 V16.0 (TIAP16)			V16.0		V16.00.00.00_27.01.00.01		
Siemens Totally Integrated Automation Portal V16 - TIACOMP CHECK Single SetupPackage V16.0 + Upd8 (TIAP16)			V16.0 + Upd8		V16.00.00.08_05.01.00.01		
Siemens Totally Integrated Automation Portal V16 - Simatic Single SetupPackage V16.0 UPD8 (TIAP16)			V16.0 UPD8		V16.00.00.08_05.01.00.01		
Siemens Totally Integrated Automation Portal V16 - WinCC Single SetupPackage V16.0 UPD8 (TIAP16)			V16.0 UPD8		V16.00.00.08_05.01.00.01		
Siemens Totally Integrated Automation Portal V16 - Openness SetupPackage V16.0 UPD8 (TIAP16)			V16.0 UPD8		V16.00.00.08_05.01.00.01		
Siemens Totally Integrated Automation Portal V16 - WinCC Transfer Mandatory Single SetupPackage V16.0 UPD8 (TIAP16)			V16.0 UPD8		V16.00.00.08_05.01.00.01		
User Management Component - UserManagementComponentx64 V2.7 Upd1 (UMC64)			V2.7 + Upd1		V02.07.00.01_01.02.00.02		
WinCC Runtime Advanced V16.0 - SIMATIC WinCC Runtime Advanced V16.0 (HMIRTM_V11)			V16.0 UPD7		V16.00.00.07_04.01.00.02		
WinCC Runtime Advanced V16.0 - HMIRTM Tagging Package 01 Single SetupPackage V16.0 UPD7 (HMIRTM_V11)			V16.0 UPD7		V16.00.00.07_04.01.00.02		
PLCSIM Advanced Single SetupPackage - PLCSIM Advanced Single SetupPackage V3.0 Upd2 (PLCSIMADV)			V3.0 + Upd2		V03.00.00.02_08.01.00.02		
SIMIT V9 - SIMIT V11.0 SP1 (SIMIT9)			V11.0 + SP1 +		V11.00.01.00_13.01.00.01		

Totally Integrated Automation Portal																																																																																						
<table><tr><th>Name</th><th>Version</th><th>Release</th></tr><tr><td>Siemens SIMIT V9 - SIMIT Simulation Platform V11.0 + SP1 + (SIMIT9)</td><td>V11.0 + SP1 +</td><td>V11.00.01.00_13.01.00.01</td></tr><tr><td>Siemens SIMIT V9 - SIMIT SU V11.0 + + (SIMIT9)</td><td>V11.0 + +</td><td>V11.00.00.00_00.00.00.08</td></tr><tr><td>Siemens SIMIT V9 - SIMIT Virtual Controller V11.0 + SP1 + (SIMIT9)</td><td>V11.0 + SP1 +</td><td>V11.00.01.00_13.01.00.01</td></tr><tr><td>Siemens Totally Integrated Automation Portal V16 - Simatic Single Setup-Package 32 Bit V16.0 (TIAP16)</td><td>V16.0</td><td>V16.00.00.00_31.02.00.01</td></tr><tr><td>Siemens Totally Integrated Automation Portal V16 - WinCC Single Setup-Package 32 Bit V16.0 (TIAP16)</td><td>V16.0</td><td>V16.00.00.00_31.02.00.01</td></tr><tr><td>SIMATIC HMI License Manager Panel Plugin (x64)</td><td>16.0.0.1</td><td>V16.00.00.01_04.01.00.01</td></tr><tr><td>Automation Access Control Component x64</td><td>05.01</td><td>K05.01.02.00_00.00.00.02</td></tr><tr><td>SIMATIC WinCC Runtime Advanced Driver (x64)</td><td>16.0.0.0</td><td>V16.00.00.00_31.02.00.01</td></tr><tr><td>ETWEventCollector</td><td>16.0.0.0</td><td>V16.00.00.00_31.02.00.01</td></tr><tr><td>Installation Integrity Validator</td><td>1.12.18.0</td><td>V01.12.18.00_00.00.00.00</td></tr><tr><td>SIMATIC NCM FWL 64</td><td>5.6.0.3</td><td>K5.6.0.3_1.1.0.2</td></tr><tr><td>NCM GPRS 64</td><td>01.02.00.00</td><td>V1.2.0.0_2.1.0.1</td></tr><tr><td>SIMATIC PLCSIM 64</td><td>16.00.00</td><td>16.00.00.00_01.00.02.01</td></tr><tr><td>SIMATIC PLCSIM Advanced Driver64</td><td>3.0.0.2</td><td>V03.00.00.02_08.01.00.02</td></tr><tr><td>SIMATIC Device Drivers</td><td>9.2</td><td>09.02.06.00_01.01.00.09</td></tr><tr><td>TelemetryConnector</td><td>1.5.0.7</td><td>V01.05.00.07_01.00.00.01</td></tr><tr><td>Automation Access Control Component</td><td>05.01</td><td>K05.01.02.00_00.00.00.02</td></tr><tr><td>Automation Software Updater</td><td>02.05.0300</td><td>V02.05.03.00_01.01.00.29</td></tr><tr><td>SIEMENS OPC</td><td>3.9</td><td>03.09.10.00_01.04.00.08</td></tr><tr><td>SIMATIC PLCSIM Advanced SimRT</td><td>3.0.0.2</td><td>V03.00.00.02_08.01.00.02</td></tr><tr><td>SIMATIC HMI ProSave</td><td>16.0.0.1</td><td>V16.00.00.01_04.01.00.01</td></tr><tr><td>SIMATIC HMI Symbol Library</td><td>16.0.0.0</td><td>V16.00.00.00_31.02.00.01</td></tr><tr><td>SIMATIC HMI Touch Input</td><td>16.0.0.7</td><td>V16.00.00.07_04.01.00.02</td></tr><tr><td>SIMATIC Device Drivers WoW</td><td>29.2</td><td>29.02.06.00_01.01.00.09</td></tr><tr><td>SIMATIC Event Database</td><td>5.6</td><td>05.06.02.03_02.01.00.01</td></tr><tr><td>SeCon</td><td>2.9</td><td>V02.09.00.00_01.03.00.01</td></tr><tr><td>WinCC Runtime Advanced Simulator</td><td>16.0.0.0</td><td>V16.00.00.00_31.02.00.01</td></tr></table>	Name	Version	Release	Siemens SIMIT V9 - SIMIT Simulation Platform V11.0 + SP1 + (SIMIT9)	V11.0 + SP1 +	V11.00.01.00_13.01.00.01	Siemens SIMIT V9 - SIMIT SU V11.0 + + (SIMIT9)	V11.0 + +	V11.00.00.00_00.00.00.08	Siemens SIMIT V9 - SIMIT Virtual Controller V11.0 + SP1 + (SIMIT9)	V11.0 + SP1 +	V11.00.01.00_13.01.00.01	Siemens Totally Integrated Automation Portal V16 - Simatic Single Setup-Package 32 Bit V16.0 (TIAP16)	V16.0	V16.00.00.00_31.02.00.01	Siemens Totally Integrated Automation Portal V16 - WinCC Single Setup-Package 32 Bit V16.0 (TIAP16)	V16.0	V16.00.00.00_31.02.00.01	SIMATIC HMI License Manager Panel Plugin (x64)	16.0.0.1	V16.00.00.01_04.01.00.01	Automation Access Control Component x64	05.01	K05.01.02.00_00.00.00.02	SIMATIC WinCC Runtime Advanced Driver (x64)	16.0.0.0	V16.00.00.00_31.02.00.01	ETWEventCollector	16.0.0.0	V16.00.00.00_31.02.00.01	Installation Integrity Validator	1.12.18.0	V01.12.18.00_00.00.00.00	SIMATIC NCM FWL 64	5.6.0.3	K5.6.0.3_1.1.0.2	NCM GPRS 64	01.02.00.00	V1.2.0.0_2.1.0.1	SIMATIC PLCSIM 64	16.00.00	16.00.00.00_01.00.02.01	SIMATIC PLCSIM Advanced Driver64	3.0.0.2	V03.00.00.02_08.01.00.02	SIMATIC Device Drivers	9.2	09.02.06.00_01.01.00.09	TelemetryConnector	1.5.0.7	V01.05.00.07_01.00.00.01	Automation Access Control Component	05.01	K05.01.02.00_00.00.00.02	Automation Software Updater	02.05.0300	V02.05.03.00_01.01.00.29	SIEMENS OPC	3.9	03.09.10.00_01.04.00.08	SIMATIC PLCSIM Advanced SimRT	3.0.0.2	V03.00.00.02_08.01.00.02	SIMATIC HMI ProSave	16.0.0.1	V16.00.00.01_04.01.00.01	SIMATIC HMI Symbol Library	16.0.0.0	V16.00.00.00_31.02.00.01	SIMATIC HMI Touch Input	16.0.0.7	V16.00.00.07_04.01.00.02	SIMATIC Device Drivers WoW	29.2	29.02.06.00_01.01.00.09	SIMATIC Event Database	5.6	05.06.02.03_02.01.00.01	SeCon	2.9	V02.09.00.00_01.03.00.01	WinCC Runtime Advanced Simulator	16.0.0.0	V16.00.00.00_31.02.00.01		
Name	Version	Release																																																																																				
Siemens SIMIT V9 - SIMIT Simulation Platform V11.0 + SP1 + (SIMIT9)	V11.0 + SP1 +	V11.00.01.00_13.01.00.01																																																																																				
Siemens SIMIT V9 - SIMIT SU V11.0 + + (SIMIT9)	V11.0 + +	V11.00.00.00_00.00.00.08																																																																																				
Siemens SIMIT V9 - SIMIT Virtual Controller V11.0 + SP1 + (SIMIT9)	V11.0 + SP1 +	V11.00.01.00_13.01.00.01																																																																																				
Siemens Totally Integrated Automation Portal V16 - Simatic Single Setup-Package 32 Bit V16.0 (TIAP16)	V16.0	V16.00.00.00_31.02.00.01																																																																																				
Siemens Totally Integrated Automation Portal V16 - WinCC Single Setup-Package 32 Bit V16.0 (TIAP16)	V16.0	V16.00.00.00_31.02.00.01																																																																																				
SIMATIC HMI License Manager Panel Plugin (x64)	16.0.0.1	V16.00.00.01_04.01.00.01																																																																																				
Automation Access Control Component x64	05.01	K05.01.02.00_00.00.00.02																																																																																				
SIMATIC WinCC Runtime Advanced Driver (x64)	16.0.0.0	V16.00.00.00_31.02.00.01																																																																																				
ETWEventCollector	16.0.0.0	V16.00.00.00_31.02.00.01																																																																																				
Installation Integrity Validator	1.12.18.0	V01.12.18.00_00.00.00.00																																																																																				
SIMATIC NCM FWL 64	5.6.0.3	K5.6.0.3_1.1.0.2																																																																																				
NCM GPRS 64	01.02.00.00	V1.2.0.0_2.1.0.1																																																																																				
SIMATIC PLCSIM 64	16.00.00	16.00.00.00_01.00.02.01																																																																																				
SIMATIC PLCSIM Advanced Driver64	3.0.0.2	V03.00.00.02_08.01.00.02																																																																																				
SIMATIC Device Drivers	9.2	09.02.06.00_01.01.00.09																																																																																				
TelemetryConnector	1.5.0.7	V01.05.00.07_01.00.00.01																																																																																				
Automation Access Control Component	05.01	K05.01.02.00_00.00.00.02																																																																																				
Automation Software Updater	02.05.0300	V02.05.03.00_01.01.00.29																																																																																				
SIEMENS OPC	3.9	03.09.10.00_01.04.00.08																																																																																				
SIMATIC PLCSIM Advanced SimRT	3.0.0.2	V03.00.00.02_08.01.00.02																																																																																				
SIMATIC HMI ProSave	16.0.0.1	V16.00.00.01_04.01.00.01																																																																																				
SIMATIC HMI Symbol Library	16.0.0.0	V16.00.00.00_31.02.00.01																																																																																				
SIMATIC HMI Touch Input	16.0.0.7	V16.00.00.07_04.01.00.02																																																																																				
SIMATIC Device Drivers WoW	29.2	29.02.06.00_01.01.00.09																																																																																				
SIMATIC Event Database	5.6	05.06.02.03_02.01.00.01																																																																																				
SeCon	2.9	V02.09.00.00_01.03.00.01																																																																																				
WinCC Runtime Advanced Simulator	16.0.0.0	V16.00.00.00_31.02.00.01																																																																																				
<table><tr><th>Products</th><th></th><th></th></tr><tr><th>Name</th><th>Version</th><th>Release</th></tr><tr><td>TIA Portal Project Server</td><td>V16.0 Upd5</td><td>V16.00.00.05_04.01.00.01</td></tr><tr><td>SIMATIC S7-PLCSIM</td><td>V16.0 Upd4</td><td>V16.00.00.04_01.00.04.01</td></tr><tr><td>TIA Administrator</td><td>V1.0</td><td>01.00.08.00_01.01.00.18</td></tr><tr><td>SINAMICS G110M, G120, G120C, G120D, G120P, G115D</td><td>V16.0 Upd5</td><td>V16.00.00.05_20.09.00.07</td></tr><tr><td>SINAMICS G130, G150, S120, S150, SINAMICS MV, S210</td><td>V16.0 Upd5</td><td>V16.00.00.05_20.09.00.07</td></tr><tr><td>SIMATIC STEP 7 Prof - STEP 7 Safety - WinCC Adv</td><td>V16.0 Upd8</td><td>V16.00.00.08_05.01.00.01</td></tr><tr><td>User Management Component</td><td>V2.7 Upd1</td><td>V02.07.00.01_01.02.00.02</td></tr><tr><td>SIMATIC WinCC Runtime Advanced Simulation</td><td>V16.0 Upd7</td><td>V16.00.00.07_04.01.00.02</td></tr><tr><td>S7-PLCSIM Advanced</td><td>V3.0 Upd2</td><td>V03.00.00.02_08.01.00.02</td></tr><tr><td>SIMIT</td><td>V11.0.1.0</td><td>V11.00.01.00_13.01.00.01</td></tr><tr><td>SIMIT SU</td><td>V11.0.0.0</td><td>V11.00.00.00_00.00.00.08</td></tr><tr><td>SIMIT MCD Add-in</td><td>V11.0.1.0</td><td>V11.00.01.00_13.01.00.01</td></tr><tr><td>Automation License Manager</td><td>V6.2 + SP5</td><td>06.02.05.00_00.00.03.23</td></tr><tr><td>S7-PLCSIM</td><td>V5.4 + SP8</td><td>V05.04.08.01_01.24.00.01</td></tr><tr><td>SIMATIC ProSave</td><td>V16.0 Upd1</td><td>V16.00.00.01_04.01.00.01</td></tr><tr><td>PUD Manager Help Viewer</td><td>V2.1 + SP1 + Upd1</td><td>V02.01.01.01_01.00.00.03</td></tr><tr><td>S7-PCT</td><td>V3.5 + SP1</td><td>K3.5.1.0_1.19.0.1</td></tr></table>	Products			Name	Version	Release	TIA Portal Project Server	V16.0 Upd5	V16.00.00.05_04.01.00.01	SIMATIC S7-PLCSIM	V16.0 Upd4	V16.00.00.04_01.00.04.01	TIA Administrator	V1.0	01.00.08.00_01.01.00.18	SINAMICS G110M, G120, G120C, G120D, G120P, G115D	V16.0 Upd5	V16.00.00.05_20.09.00.07	SINAMICS G130, G150, S120, S150, SINAMICS MV, S210	V16.0 Upd5	V16.00.00.05_20.09.00.07	SIMATIC STEP 7 Prof - STEP 7 Safety - WinCC Adv	V16.0 Upd8	V16.00.00.08_05.01.00.01	User Management Component	V2.7 Upd1	V02.07.00.01_01.02.00.02	SIMATIC WinCC Runtime Advanced Simulation	V16.0 Upd7	V16.00.00.07_04.01.00.02	S7-PLCSIM Advanced	V3.0 Upd2	V03.00.00.02_08.01.00.02	SIMIT	V11.0.1.0	V11.00.01.00_13.01.00.01	SIMIT SU	V11.0.0.0	V11.00.00.00_00.00.00.08	SIMIT MCD Add-in	V11.0.1.0	V11.00.01.00_13.01.00.01	Automation License Manager	V6.2 + SP5	06.02.05.00_00.00.03.23	S7-PLCSIM	V5.4 + SP8	V05.04.08.01_01.24.00.01	SIMATIC ProSave	V16.0 Upd1	V16.00.00.01_04.01.00.01	PUD Manager Help Viewer	V2.1 + SP1 + Upd1	V02.01.01.01_01.00.00.03	S7-PCT	V3.5 + SP1	K3.5.1.0_1.19.0.1																													
Products																																																																																						
Name	Version	Release																																																																																				
TIA Portal Project Server	V16.0 Upd5	V16.00.00.05_04.01.00.01																																																																																				
SIMATIC S7-PLCSIM	V16.0 Upd4	V16.00.00.04_01.00.04.01																																																																																				
TIA Administrator	V1.0	01.00.08.00_01.01.00.18																																																																																				
SINAMICS G110M, G120, G120C, G120D, G120P, G115D	V16.0 Upd5	V16.00.00.05_20.09.00.07																																																																																				
SINAMICS G130, G150, S120, S150, SINAMICS MV, S210	V16.0 Upd5	V16.00.00.05_20.09.00.07																																																																																				
SIMATIC STEP 7 Prof - STEP 7 Safety - WinCC Adv	V16.0 Upd8	V16.00.00.08_05.01.00.01																																																																																				
User Management Component	V2.7 Upd1	V02.07.00.01_01.02.00.02																																																																																				
SIMATIC WinCC Runtime Advanced Simulation	V16.0 Upd7	V16.00.00.07_04.01.00.02																																																																																				
S7-PLCSIM Advanced	V3.0 Upd2	V03.00.00.02_08.01.00.02																																																																																				
SIMIT	V11.0.1.0	V11.00.01.00_13.01.00.01																																																																																				
SIMIT SU	V11.0.0.0	V11.00.00.00_00.00.00.08																																																																																				
SIMIT MCD Add-in	V11.0.1.0	V11.00.01.00_13.01.00.01																																																																																				
Automation License Manager	V6.2 + SP5	06.02.05.00_00.00.03.23																																																																																				
S7-PLCSIM	V5.4 + SP8	V05.04.08.01_01.24.00.01																																																																																				
SIMATIC ProSave	V16.0 Upd1	V16.00.00.01_04.01.00.01																																																																																				
PUD Manager Help Viewer	V2.1 + SP1 + Upd1	V02.01.01.01_01.00.00.03																																																																																				
S7-PCT	V3.5 + SP1	K3.5.1.0_1.19.0.1																																																																																				

Totally Integrated Automation Portal

ChemicalProcess

PLC_1 [CPU 1511-1 PN]

PLC_1

General\Project information

Name	PLC_1	Author	mika3	Comment	
Rack	0	Slot	1		

General\Catalog information

Short designation	CPU 1511-1 PN	Description	CPU with display; work memory 150 KB code and 1 MB data; 60 ns bit operation time; 4-stage protection concept, technology functions: motion control, closed-loop control, counting and measuring; tracing; Runtime options; isochronous mode (central); for all PROFINET interfaces: transport protocol TCP/IP, secure Open User Communication, S7 communication, S7 routing, IP forwarding, Web server, DNS client, OPC UA: Server DA, Client DA, methods, companion specifications; PROFINET IO controller, supports RT/IRT, performance upgrade PROFINET V2.3, 2 ports, I-Device, MRP, MRPD, isochronous mode; firmware V2.8		
Firmware version	V2.8				

General\Identification & Maintenance

Plant designation		Location identifier		Installation date	2021-05-25 07:35:19.863
Additional information					

General\Checksums

Text lists	CB 3F BA AA D7 54 DC 4F	Software	Not available (compile necessary)		
------------	-------------------------	----------	-----------------------------------	--	--

PROFINET interface [X1]\General

Name	PROFINET interface_1	Author	mika3	Comment	
------	----------------------	--------	-------	---------	--

PROFINET interface [X1]\Ethernet addresses\Interface networked with

Subnet:	PN/IE_1				
---------	---------	--	--	--	--

PROFINET interface [X1]\Ethernet addresses\IP protocol

IP configuration	Set IP address in the project	IP address:	192.168.0.1	Subnet mask:	255.255.255.0
Use router	False				

PROFINET interface [X1]\Ethernet addresses\PROFINET

PROFINET device name is set directly at the device	False	Generate PROFINET device name automatically	True	PROFINET device name:	plc_1.profinet interface_1
Converted name:	plcxb1.profinetxainterfacexb1036c	Device number:	0		

PROFINET interface [X1]\Time-of-day synchronization\NTP mode

Note	Time synchronization for all PROFINET interfaces take place within the settings for time synchronization of the PROFINET interface [X1].	Enable time synchronization via NTP server	False		IP addresses
Server 1	0.0.0.0	Server 2	0.0.0.0	Server 3	0.0.0.0
Server 4	0.0.0.0	Update interval	10s		

PROFINET interface [X1]\Operating mode

IO controller	True	IO system		Device number	0
IO device	False				

PROFINET interface [X1]\Advanced options\Interface options

Call the user program if communication errors occur	False	Support device replacement without exchangeable medium	True	Permit overwriting of device names of all assigned IO devices	False
Limit data infeed into the network	True	Use IEC V2.2 LLDP mode	False	Keep-Alive connection monitoring:	30s

PROFINET interface [X1]\Advanced options\Media redundancy

MRP domain	mrpdomain-1	Media redundancy role:	Not device in the ring		
------------	-------------	------------------------	------------------------	--	--

PROFINET interface [X1]\Advanced options\Real time settings\IO communication

Send clock:	1.000ms				
-------------	---------	--	--	--	--

PROFINET interface [X1]\Advanced options\Real time settings\Synchronization

Sync domain:	Sync-Domain_1	Synchronization role:	Unsynchronized	RT class:	RT,IRT
--------------	---------------	-----------------------	----------------	-----------	--------

PROFINET interface [X1]\Advanced options\Real time settings\Real time options


Calculated bandwidth for cyclic IO data:	0.000ms	Calculated bandwidth for cyclic IO data:	0.000%		
--	---------	--	--------	--	--


PROFINET interface [X1]\Advanced options\Port [X1 P1 R]\General

Name	Port_1	Author	mika3	Comment	
------	--------	--------	-------	---------	--

PROFINET interface [X1]\Advanced options\Port [X1 P1 R]\Port interconnection\Local port:

Local port:	PLC_1\PROFINET interface_1 [X1]\Port_1 [X1 P1 R]	Medium:	Copper	Cable name:	---
-------------	--	---------	--------	-------------	-----



Totally Integrated Automation Portal						
PROFINET interface [X1]\Advanced options\Port [X1 P1 R]\Port interconnection\Partner port:						
	Monitoring of partner port is not possible	Alternative partners	False	Partner port:	Any partner	
PROFINET interface [X1]\Advanced options\Port [X1 P1 R]\Port options\Activate						
Activate this port for use	True					
PROFINET interface [X1]\Advanced options\Port [X1 P1 R]\Port options\Connection						
Transmission rate / duplex:	Automatic	Monitor	False	Enable autonegotiation	True	
PROFINET interface [X1]\Advanced options\Port [X1 P1 R]\Port options\Boundaries						
End of detection of accessible devices	False	End of topology discovery	False	End of the sync domain	False	
PROFINET interface [X1]\Advanced options\Port [X1 P2 R]\General						
Name	Port_2	Author	mika3	Comment		
PROFINET interface [X1]\Advanced options\Port [X1 P2 R]\Port interconnection\Local port:						
Local port:	PLC_1\PROFINET interface_1 [X1]\Port_2 [X1 P2 R]		Medium:	Copper	Cable name:	---
						
PROFINET interface [X1]\Advanced options\Port [X1 P2 R]\Port interconnection\Partner port:						
	Monitoring of partner port is not possible	Alternative partners	False	Partner port:	Any partner	
PROFINET interface [X1]\Advanced options\Port [X1 P2 R]\Port options\Activate						
Activate this port for use	True					
PROFINET interface [X1]\Advanced options\Port [X1 P2 R]\Port options\Connection						
Transmission rate / duplex:	Automatic	Monitor	False	Enable autonegotiation	True	
PROFINET interface [X1]\Advanced options\Port [X1 P2 R]\Port options\Boundaries						
End of detection of accessible devices	False	End of topology discovery	False	End of the sync domain	False	
PROFINET interface [X1]\Web server access						
Note	The Web server must also be activated in the properties of the PLC.		Enable Web server via IP address of this interface	False		
Startup						
Startup after POWER ON	Warm restart - Operating mode before POWER OFF	Comparison preset to actual configuration	Startup CPU even if mismatch	Configuration time	60000ms	
Cycle						
Maximum cycle time	150ms			Enable minimum cycle time for cyclic OBs	True	
Minimum cycle time	1ms					
Communication load						
Cycle load due to communication	50%					
System and clock memory\System memory bits						
Enable the use of system memory byte	False	Address of system memory byte (MBx)	1	First cycle		
Diagnostic status changed		Always 1 (high)		Always 0 (low)		
System and clock memory\Clock memory bits						
Enable the use of clock memory byte	False	Address of clock memory byte (MBx)	0	10 Hz clock		
5 Hz clock		2.5 Hz clock		2 Hz clock		
1.25 Hz clock		1 Hz clock		0.625 Hz clock		
0.5 Hz clock						
SIMATIC Memory Card\Diagnostics						
Aging of the SIMATIC memory card	False	Threshold value	80%			
System diagnostics\General						
Activate system diagnostics for this device	True	Report network faults as maintenance instead of fault	False			
PLC alarms\General						
Central alarm management in the PLC	True					
Web server\General						
Activate web server on this module	False	Permit access only with HTTPS	True			
Web server\Automatic update						
Enable automatic update	True	Update interval	0s			
Web server\User management						
User name			User rights			
Everybody						
Web server\User-defined web pages						
Application name	HTML source path	Default HTML page	Files with dynamic content	Web DB number	Fragment DB number	
		index.htm	.htm;.html	333	334	
Web server\Overview of interfaces						
Device		Interface		Enabled web server access		
PLC_1		PROFINET interface_1		False		

Totally Integrated Automation Portal		
ChemicalProcess / PLC_1 [CPU 1511-1 PN] Software units This folder is empty.		

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks


Main [OB1]

Main Properties							
General							
Name	Main	Number	1	Type	OB	Language	FBD
Numbering	Automatic						
Information							
Title	"Main Program Sweep (Cycle)"	Author		Comment	This is where physical world meets the digital world. Main cyclic control block. Calls HMI handling, operating modes, safety/fault logic, sensor scaling, actuator control, and process sequence in defined order.	Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Comment
▼ Input			
Initial_Call	Bool		Initial call of this OB
Remanence	Bool		=True, if remanent data are available
▼ Temp			
Scaled_WI512	Real		WT/WI-512 sensor´s scaled value.
Scaled_LI515	Real		LT/LI-515 sensor´s scaled value
Scaled_TI517	Real		TT/TI-517 sensor´s scaled value
Scaled_TI518	Real		TT/TI-518 sensor´s scaled value
Scaled_FIC516	Real		Current sensor for PumpM003
M003ScaledStatus	Word		
Constant			


Network 1: HMI

Not in use for now. Reads operator commands and prepares start, stop, reset, auto/manual selections.




Network 2: Automode

Creates automatic operation enable signal from HMI mode selection and start/stop commands.




Network 3: ManualMode

Creates manual operation enable signal for direct operator-controlled device operation.




Network 4: Emergency Stop

Processes emergency stop input and creates global emergency stop active signal.




Network 5: Fault

Collects process, device, sensor, and emergency stop faults into one fault status.




Network 6: TestMode

Creates global all outputs ON/OFF test commands.




Network 7: Sensors Scalings

Scales raw analog sensor values into engineering units for process logic.




Network 8: PID FIC-516 /M003



Network 9: Valves


Calls valve FB instances and maps sequence/manual commands to physical valve outputs.



Network 10: Motors

Calls motor FB instances and maps sequence/manual commands to physical motor outputs.


Calls motor FB instances and maps sequence/manual commands to physical motor outputs.



Network 11: Process Sequence

Runs GRAPH process sequence for automatic batch operation.

Runs GRAPH process sequence for automatic batch operation.



Reserved for future PID, VFD, alarms, diagnostics, or reporting logic.

Reserved for future PID, VFD, alarms, diagnostics, or reporting logic.

ProcessSequence [FB1]

--	--	--

Totally Integrated Automation Portal									
Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
M003_TK	Bool	false	Non-retain	True	True	True	False		M003.TK isTemperature pro-tecton signal of Motor M003
M003_R	Bool	false	Non-retain	False	False	False	False		M003.R is Reset signal of Motor M003
StopandWait	Bool	false	Non-retain	True	True	True	False		Stop the Process and goest back S and wait until press-ed start manually
InOut									
▼ Static									
▼ RT_DATA	G7_RTData-Plus_V6		Non-retain	False	False	False	True		Internal data area
VERSION	String[10]	'V6.0'	Non-retain	False	False	False	False		
S_DISPLAY	Int	0	Non-retain	False	False	False	False		
S_SEL_OLD	Int	0	Non-retain	False	False	False	False		
S_DISPIDX	USInt	255	Non-retain	False	False	False	False		
T_DISPIDX	USInt	255	Non-retain	False	False	False	False		
▼ MOP_EDGE	G7_MOP-Plus_V6		Non-retain	False	False	False	True		
AUTO	Bool	false	Non-retain	False	False	False	False		
MAN	Bool	false	Non-retain	False	False	False	False		
TAP	Bool	false	Non-retain	False	False	False	False		
TOP	Bool	false	Non-retain	False	False	False	False		
ACK_S	Bool	false	Non-retain	False	False	False	False		
REG_S	Bool	false	Non-retain	False	False	False	False		
T_PREV	Bool	false	Non-retain	False	False	False	False		
T_NEXT	Bool	false	Non-retain	False	False	False	False		
LOCK	Bool	false	Non-retain	False	False	False	False		
SUP	Bool	false	Non-retain	False	False	False	False		
ACKREQ	Bool	false	Non-retain	False	False	False	False		
SSKIP	Bool	false	Non-retain	False	False	False	False		
OFF	Bool	false	Non-retain	False	False	False	False		
INIT	Bool	false	Non-retain	False	False	False	False		
HALT	Bool	false	Non-retain	False	False	False	False		
TMS_HALT	Bool	false	Non-retain	False	False	False	False		
OPS_ZERO	Bool	false	Non-retain	False	False	False	False		
SACT_DISP	Bool	false	Non-retain	False	False	False	False		
SEF_DISP	Bool	false	Non-retain	False	False	False	False		
SALL_DISP	Bool	false	Non-retain	False	False	False	False		
S_PREV	Bool	false	Non-retain	False	False	False	False		
S_NEXT	Bool	false	Non-retain	False	False	False	False		
S_SELOK	Bool	false	Non-retain	False	False	False	False		
S_ON	Bool	false	Non-retain	False	False	False	False		
S_OFF	Bool	false	Non-retain	False	False	False	False		
T_PUSH	Bool	false	Non-retain	False	False	False	False		
REG	Bool	false	Non-retain	False	False	False	False		
ACK	Bool	false	Non-retain	False	False	False	False		
IL_PERM	Bool	false	Non-retain	False	False	False	False		
T_PERM	Bool	false	Non-retain	False	False	False	False		
ILP_MAN	Bool	false	Non-retain	False	False	False	False		
LMODE	Bool	false	Non-retain	False	False	False	False		
RESET_CRIT	Bool	false	Non-retain	False	False	False	False		
▼ MOP	G7_MOP-Plus_V6		Non-retain	False	False	False	True		
AUTO	Bool	true	Non-retain	False	False	False	False		
MAN	Bool	false	Non-retain	False	False	False	False		
TAP	Bool	false	Non-retain	False	False	False	False		
TOP	Bool	false	Non-retain	False	False	False	False		
ACK_S	Bool	false	Non-retain	False	False	False	False		
REG_S	Bool	false	Non-retain	False	False	False	False		
T_PREV	Bool	false	Non-retain	False	False	False	False		
T_NEXT	Bool	false	Non-retain	False	False	False	False		
LOCK	Bool	true	Non-retain	False	False	False	False		
SUP	Bool	true	Non-retain	False	False	False	False		
ACKREQ	Bool	true	Non-retain	False	False	False	False		
SSKIP	Bool	false	Non-retain	False	False	False	False		
OFF	Bool	false	Non-retain	False	False	False	False		
INIT	Bool	true	Non-retain	False	False	False	False		
HALT	Bool	false	Non-retain	False	False	False	False		
TMS_HALT	Bool	false	Non-retain	False	False	False	False		
OPS_ZERO	Bool	false	Non-retain	False	False	False	False		
SACT_DISP	Bool	true	Non-retain	False	False	False	False		
SEF_DISP	Bool	false	Non-retain	False	False	False	False		
SALL_DISP	Bool	false	Non-retain	False	False	False	False		
S_PREV	Bool	false	Non-retain	False	False	False	False		

Totally Integrated Automation Portal									
Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
SINI_OFFSET	UInt	0	Non-retain	False	False	False	False		
LSTT_OFFSET	UInt	16	Non-retain	False	False	False	False		
ATAJ_OFFSET	UInt	28	Non-retain	False	False	False	False		
ATAB_OFFSET	UInt	40	Non-retain	False	False	False	False		
PSTT_OFFSET	UInt	52	Non-retain	False	False	False	False		
NSTT_OFFSET	UInt	64	Non-retain	False	False	False	False		
ASSJ_OFFSET	UInt	76	Non-retain	False	False	False	False		
ASSB_OFFSET	UInt	94	Non-retain	False	False	False	False		
PTTS_OFFSET	UInt	112	Non-retain	False	False	False	False		
NTTS_OFFSET	UInt	130	Non-retain	False	False	False	False		
SW_SQTS_OFFSET	UInt	148	Non-retain	False	False	False	False		
SWITCH_OFFSET	UInt	166	Non-retain	False	False	False	False		
TVX_OFFSET	UInt	203	Non-retain	False	False	False	False		
TTX_OFFSET	UInt	219	Non-retain	False	False	False	False		
TSX_OFFSET	UInt	235	Non-retain	False	False	False	False		
S00X_OFFSET	UInt	251	Non-retain	False	False	False	False		
SOFFX_OFFSET	UInt	267	Non-retain	False	False	False	False		
SONX_OFFSET	UInt	283	Non-retain	False	False	False	False		
SAX_OFFSET	UInt	299	Non-retain	False	False	False	False		
SERRX_OFFSET	UInt	315	Non-retain	False	False	False	False		
SMX_OFFSET	UInt	334	Non-retain	False	False	False	False		
S0X_OFFSET	UInt	353	Non-retain	False	False	False	False		
S1X_OFFSET	UInt	372	Non-retain	False	False	False	False		
THRESHOLD_SUP	USInt	0	Non-retain	False	False	False	False		
THRESHOLD_WARN	USInt	0	Non-retain	False	False	False	False		
▼ GC_FLAGS	G7_GCFlags-Plus_V6		Non-retain	False	False	False	True		
COND_ED	USInt	16#E3	Non-retain	False	False	False	False		
SSKIP_ON	Bool	false	Non-retain	False	False	False	False		
ACK_REQ	Bool	true	Non-retain	False	False	False	False		
ILP_MAN	Bool	false	Non-retain	False	False	False	False		
SWM_LOCKED	Bool	false	Non-retain	False	False	False	False		
SET_ENO	Bool	false	Non-retain	False	False	False	False		
IL_CAT	USInt	1	Non-retain	False	False	False	False		
IL_SUBCAT_1	USInt	0	Non-retain	False	False	False	False		
IL_SUBCAT_2	USInt	0	Non-retain	False	False	False	False		
REACT_CAT	USInt	1	Non-retain	False	False	False	False		
REACT_SUBCAT_1	USInt	0	Non-retain	False	False	False	False		
REACT_SUBCAT_2	USInt	0	Non-retain	False	False	False	False		
WARN_CAT	USInt	2	Non-retain	False	False	False	False		
WARN_SUBCAT_1	USInt	0	Non-retain	False	False	False	False		
WARN_SUBCAT_2	USInt	0	Non-retain	False	False	False	False		
CRIT_ON	Bool	false	Non-retain	False	False	False	False		
▼ Trans1	G7_Transition-Plus_V6		Non-retain	False	False	False	True		Transition structure
TV	Bool	false	Non-retain	False	False	False	False		
TT	Bool	false	Non-retain	False	False	False	False		
TS	Bool	false	Non-retain	False	False	False	False		
TNO	Int	1	Non-retain	False	False	False	False		
CRIT	DWord	16#0	Non-retain	False	False	False	False		
CRIT_OLD	DWord	16#0	Non-retain	False	False	False	False		
CRIT_FLT	DWord	16#0	Non-retain	False	False	False	False		
▼ Trans2	G7_Transition-Plus_V6		Non-retain	False	False	False	True		Transition structure
TV	Bool	false	Non-retain	False	False	False	False		
TT	Bool	false	Non-retain	False	False	False	False		
TS	Bool	false	Non-retain	False	False	False	False		
TNO	Int	2	Non-retain	False	False	False	False		
CRIT	DWord	16#0	Non-retain	False	False	False	False		
CRIT_OLD	DWord	16#0	Non-retain	False	False	False	False		
CRIT_FLT	DWord	16#0	Non-retain	False	False	False	False		
▼ Trans3	G7_Transition-Plus_V6		Non-retain	False	False	False	True		Transition structure
TV	Bool	false	Non-retain	False	False	False	False		
TT	Bool	false	Non-retain	False	False	False	False		
TS	Bool	false	Non-retain	False	False	False	False		
TNO	Int	3	Non-retain	False	False	False	False		
CRIT	DWord	16#0	Non-retain	False	False	False	False		
CRIT_OLD	DWord	16#0	Non-retain	False	False	False	False		
CRIT_FLT	DWord	16#0	Non-retain	False	False	False	False		
▼ Trans4	G7_Transition-Plus_V6		Non-retain	False	False	False	True		Transition structure
TV	Bool	false	Non-retain	False	False	False	False		
TT	Bool	false	Non-retain	False	False	False	False		

Totally Integrated Automation Portal									
Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
CRIT_OLD	DWord	16#0	Non-retain	False	False	False	False		
CRIT_FLT	DWord	16#0	Non-retain	False	False	False	False		
▼ Start	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	1	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Fill NaOH	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	2	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Fill Powder M001	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		

Totally Integrated Automation Portal									
Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	3	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Start Mixing	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	4	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Empty MIX Tank	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	5	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Stop Water	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		

Totally Integrated Automation Portal									
Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	6	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Close NaOH valve	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	7	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Powder Motor Stop	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	8	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		

Totally Integrated Automation Portal									
Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
SNO	Int	11	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Exit valve open	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	12	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Step13	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	13	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Not to Storage	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		

Totally Integrated Automation Portal									
Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	14	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Exit valve close	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	15	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Valve 521 Stays open	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	16	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		

Totally Integrated Automation Portal									
Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Fill water	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	17	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
▼ Step18	G7_StepPlus_V6		Non-retain	False	False	False	True		Step structure
S1	Bool	false	Non-retain	False	False	False	False		
L1	Bool	false	Non-retain	False	False	False	False		
V1	Bool	false	Non-retain	False	False	False	False		
R1	Bool	false	Non-retain	False	False	False	False		
A1	Bool	false	Non-retain	False	False	False	False		
S0	Bool	false	Non-retain	False	False	False	False		
L0	Bool	false	Non-retain	False	False	False	False		
V0	Bool	false	Non-retain	False	False	False	False		
X	Bool	false	Non-retain	False	False	False	False		
LA	Bool	false	Non-retain	False	False	False	False		
VA	Bool	false	Non-retain	False	False	False	False		
RA	Bool	false	Non-retain	False	False	False	False		
AA	Bool	false	Non-retain	False	False	False	False		
SS	Bool	false	Non-retain	False	False	False	False		
LS	Bool	true	Non-retain	False	False	False	False		
VS	Bool	false	Non-retain	False	False	False	False		
SNO	Int	18	Non-retain	False	False	False	False		
T	Time	T#0ms	Non-retain	False	False	False	False		
U	Time	T#0ms	Non-retain	False	False	False	False		
T_MAX	Time	T#10S	Non-retain	False	False	False	False		
T_WARN	Time	T#7S	Non-retain	False	False	False	False		
CRIT_LOC	DWord	16#0	Non-retain	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	Non-retain	False	False	False	False		
SM	Bool	false	Non-retain	False	False	False	False		
H_IL_ERR	Byte	16#0	Non-retain	False	False	False	False		
H_SV_FLT	Byte	16#04	Non-retain	False	False	False	False		
Temp									
Constant									

Alarms

Enable alarms			True		
Category		Category enabler			Display class
Error					0
Warning					0
Info					0
Category 4					0
Category 5					0
Category 6					0
Category 7					0
Category 8					0
Category for inter-locks	Error	Subcategory 1 for in-terlocks			
Category for supervi-sions	Error	Subcategory 1 for su-pervisions			

--	--	--

Category for GRAPH warnings	Warning	Subcategory 1 for GRAPH warnings		Subcategory 2 for GRAPH warnings	
-----------------------------	---------	----------------------------------	--	----------------------------------	--

Symbol	Address	Type	Comment
--------	---------	------	---------


Permanent pre-instructions

1:



Sequences (1)

1:



S1 - [Initial step]:Start

Totally Integrated Automation Portal

Interlock -(c)-:

Interlock alarm

Alarm text

#Auto

#Manual

#StopandWait

Interlock

(c)

#Manual

#Auto

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

(v)

Actions:

Actions:

Interlock	Event	Qualifier	Action
		N	#Initiate

T1:Trans1

#Initiate

S2:Fill NaOH

600Kg to 1200kg in weight sensor is 600Kg of NaOH.

Interlock -(c)-:

Interlock alarm

Alarm text

#WL_512

<=

Real

40.0

#GSV_510

#M001_ST

#M002_ST

Interlock

(c)

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

(v)

Actions:

Actions:

Interlock	Event	Qualifier	Action
C	S1	N	#"HS_511_Open_"

T2:Trans2

#WL_512

>=

Real

60.0

S3:Fill Powder M001

1200-1800KG in wight sensor = 600Kg of Powder

Interlock -(c)-:

Interlock alarm

Alarm text

Totally Integrated Automation Portal

#GSV_510

#M002_ST

#LSA_513

#M001_F

#M001_TK

#GSV_511

Interlock

(c)

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

(v)

Actions:

Actions:

Interlock	Event	Qualifier	Action
C		N	#M001_ST

T3:Trans3

#WL_512

>=

Real

90.0

S4:Start Mixing

Interlock -(c)-:

Interlock alarm

Alarm text

#GSV_510

#GSV_511

#M001_ST

#M002_F

Interlock

(c)

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

(v)

Actions:

Actions:

Interlock	Event	Qualifier	Action
C		N	CALL TOF TIME, "MixTankMotorTlmer" (IN :=#M002_ST PT := #SetTimeForMixing Q => #M002_R ET=> #SetElapseTimeforMixing)

T4:Trans4

"MixTankMotorTlmer".PT

==

Time

T#0s

S5:Empty MIX Tank

Interlock -(c)-:

Interlock alarm

Alarm text

Totally Integrated Automation Portal		
--------------------------------------	--	--

#LL_515

<

Real

80.0

#GSV_510

#GSV_511

#M002_ST

#M001_ST

Interlock

(C)

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

(v)

Actions:

Actions:

Interlock	Event	Qualifier	Action
C		N	#HS_514_Open

T5:Trans5

#M002_R

S6:Stop Water

If Valve opens have to make sure it closes.

Interlock -(c)-:

Interlock alarm

Alarm text

#WL_512

>=

Real

30.0

Interlock

(C)

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

(v)

Actions:

Actions:

Interlock	Event	Qualifier	Action
C	S1	N	#HS_510_Close

T2:Trans2

#WL_512

>=

Real

60.0

S7:Close NaOH valve

Interlock -(c)-:

Interlock alarm

Alarm text

#WL_512

=

Real

60.0

Interlock

(C)

Totally Integrated Automation Portal		
--------------------------------------	--	--

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

(v)

Actions:

Actions:

Interlock	Event	Qualifier	Action
C	S1	N	#HS_511_Close

T3:Trans3

#WL_512

>=

Real

90.0

S8:Powder Motor Stop

Interlock -(c)-:

Interlock alarm

Alarm text

#WL_512

>=

Real

90.0

Interlock

(c)

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

(v)

Actions:

Actions:

Interlock	Event	Qualifier	Action
C		N	#M001_R

T4:Trans4

"MixTankMotorTimer".PT

==

Time

T#0s

S9:Stop Mixing

Interlock -(c)-:

Interlock alarm

Alarm text

"MixTankMotorTimer".PT

==

Time

T#0s

Interlock

(c)

Supervision -(v)-:

Supervision alarm

Alarm text

--	--	--

Totally Integrated Automation Portal

Supervision

{ v }

Actions:

Actions:

Interlock	Event	Qualifier	Action
C		N	#M002_R

T5:Trans5

#M002_R

S10:Empty Storage Tank

Interlock -(c)-:

Interlock alarm

Alarm text

#GSV_514

#LL_515

>

Real

70.0

#M003_F

#M003_TK

#M003_R

Interlock

{ c }

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

{ v }

Actions:

Actions:

Interlock	Event	Qualifier	Action
C		N	#M003_ST

T6:Trans6

#M003_ST

S11:Stop emptying

Interlock -(c)-: Stop Emptying

Interlock alarm

Alarm text

#WL_512

<=

Real

2.0

Interlock

{ c }

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

{ v }

Totally Integrated Automation Portal		
--------------------------------------	--	--

Actions:

Actions:			
Interlock	Event	Qualifier	Action
C		N	#HS_514_Close

T7:Trans7

#LI_515

<

Real

3500.0

S12:Exit valve open

Interlock -(c)-:

Interlock alarm	
Alarm text	

#M003_ST

Interlock

(c)

Supervision -(v)-:

Supervision alarm	
Alarm text	

Supervision

(v)

Actions:

Actions:			
Interlock	Event	Qualifier	Action
C		N	#HS_519_Open

T8:Trans8

#LI_515

<

Real

10.0

#FIC_516

<

Real

10.0

S13:Step13

Interlock -(c)-:

Interlock alarm	
Alarm text	

#LI_515

<

Real

5.0

#FIC_516

<

Real

5.0

Interlock

(c)

Supervision -(v)-:

Supervision

(v)

Actions:

Totally Integrated Automation Portal

Interlock	Event	Qualifier	Action

T9:Trans9

#M003_R

S14:Not to Storage

Interlock -(c)-:

Interlock alarm

Alarm text

#M003_ST

Interlock

(C)

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

(v)

Actions:

Actions:

Interlock	Event	Qualifier	Action
		N	#HS_521_Close

T8:Trans8

#LI_515

<

Real

10.0

#FIC_516

<

Real

10.0

S15:Exit valve close

Interlock -(c)-:

Interlock alarm

Alarm text

#M003_R

#FIC_516

<

Real

5.0

Interlock

(C)

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

(v)

Actions:

Actions:

Interlock	Event	Qualifier	Action
		N	#HS_519_Close

T10:Trans10

#HS_519_Close

#HS_521_Open

Totally Integrated Automation Portal		
--------------------------------------	--	--

S16:Valve 521 Stays open

Interlock -(c)-:

Interlock alarm

Alarm text

#M003_R

#FIC_516

<

Real

5.0

Interlock

(c)

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

(v)

Actions:

Actions:

Interlock	Event	Qualifier	Action
C		N	#HS_521_Open

T10:Trans10

#HS_519_Close

#HS_521_Open

S17:Fill water

1Litre = 1Kg, 0-600Kg in Weight sensor is 600litres of Water
For forcing value of sensors converts kg value to Siemens analog raw value (0...27648).
For 200KG = 2765

Interlock -(c)-:

Interlock alarm

Alarm text

#WL_512

<=

Real

5.0

#HS_510_Close

#GSV_511

#M001_ST

#M002_ST

Interlock

(c)

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

(v)

Actions:

Actions:

Interlock	Event	Qualifier	Action
C		N	#HS_510_Open

T11:Trans11

#WL_512

>=

Real

600.0

S18:Step18

--	--	--

Totally Integrated Automation Portal		
--------------------------------------	--	--

Interlock -(c)-:

Interlock alarm

Alarm text

Interlock

{ c }

Supervision -(v)-:

Supervision alarm

Alarm text

Supervision

{ v }

Actions:

Actions:

Interlock	Event	Qualifier	Action
		N	#StopandWait

T12:Trans12

#StopandWait

Permanent post-instructions

1:

--	--	--

ProcessSequence_DB [DB3]

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
WI_512	Real	0.0	False	True	True	True	False		WT-512 is Weight Sensor and connected in OB
LSA_513	Bool	false	False	True	True	True	False		LS-513 Powder Low level Button
SetTimeForMixing	Time	T#0ms	False	True	True	True	False		Mlx Tank Motor timing
TI_517	Real	0.0	False	True	True	True	False		
TI_518	Real	0.0	False	True	True	True	False		
FIC_516	Real	0.0	False	True	True	True	False		FIC-516 is Pressure sensor Integrated with M003
LI_515	Real	0.0	False	True	True	True	False		LT-515 Level indicative sensor
ACK_EF	Bool	false	False	False	False	False	False		Acknowledge all errors and faults
Auto	Bool	false	False	True	True	True	False		Automode makes sytem run automatically until pressed stop.
Manual	Bool	false	False	True	True	True	False		Manual mode make user start every-time time the storage tank is emptied.
M003_SP	Real	0.0	False	True	True	True	False		PIDTulo
▼ Output									
Initiate	Bool	false	False	True	True	True	False		Start initiates the program
HS_510_Open	Bool	false	False	True	True	True	False		ZSC-510 is Valve open signal GSV-510.
HS_510_Close	Bool	false	False	True	True	True	False		ZSC-510 Valve close signal for GSV-510.
GSV_510	Bool	false	False	True	True	True	False		GSV_510 Valve
HS_511_Open_	Bool	false	False	True	True	True	False		ZSO-511 is Valve open signal GSV-511.
HS_511_Close	Bool	false	False	True	True	True	False		ZSC-511 Valve close signal
GSV_511	Bool	false	False	True	True	True	False		GSV-511 Valve
HS_514_Open	Bool	false	False	False	False	False	False		ZSO-514 is Valve open signal for GSV-514
HS_514_Close	Bool	false	False	True	True	True	False		ZSC-514 is valve close signal for GSV-514
GSV_514	Bool	false	False	True	True	True	False		Valve GSV-514.
HS_519_Open	Bool	false	False	True	True	True	False		ZSO-519 is valve open signal for GSV-519
HS_519_Close	Bool	false	False	False	False	False	False		ZSC-519 is Valve close signal for GSV-519
GSV_519	Bool	false	False	True	True	True	False		
HS_521_Open	Bool	false	False	True	True	True	False		ZSO-521 valve open signal for GSV-521
HS_521_Close	Bool	false	False	True	True	True	False		ZSC-521 close valve signal for GSV_521
GSV_521	Bool	false	False	True	True	True	False		
SetElapseTimeforMixing	Time	T#0ms	False	True	True	True	False		Elaspse time for mix tank motor
M001_ST	Bool	false	False	False	False	False	False		M001.ST is Powder Motor start signal.
M001_TK	Bool	false	False	True	True	True	False		M001.TK is Temperature protection of POWder Motor.
M001_F	Bool	false	False	True	True	True	False		M001.F fault signal of Powder Motor
M001_R	Bool	false	False	True	True	True	False		Reset of Powder Motor
M002_ST	Bool	false	False	True	True	True	False		M002.ST is Mixtank Motor signal.
M002_TK	Bool	false	False	True	True	True	False		
M002_F	Bool	false	False	True	True	True	False		Mator Fault signal For Mix Tank motor
M002_R	Bool	false	False	True	True	True	False		Reset for Mixing Motor
M003_ST	Bool	false	False	True	True	True	False		M003.ST is Start signal of Motor M003
M003_F	Bool	false	False	True	True	True	False		M003.F is Fault signal of Motor M003
M003_TK	Bool	false	False	True	True	True	False		M003.TK isTemperature protection signal of Motor M003
M003_R	Bool	false	False	False	False	False	False		M003.R is Reset signal of Motor M003
StopandWait	Bool	false	False	True	True	True	False		Stop the Process and goest back S and wait until pressed start manually
InOut									
▼ Static									

Totally Integrated Automation Portal										
Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment	
▼ RT_DATA	G7_RTData-Plus_V6		False	False	False	False	True		Internal data area	
VERSION	String[10]	'V6.0'	False	False	False	False	False			
S_DISPLAY	Int	0	False	False	False	False	False			
S_SEL_OLD	Int	0	False	False	False	False	False			
S_DISPIDX	USInt	255	False	False	False	False	False			
T_DISPIDX	USInt	255	False	False	False	False	False			
▼ MOP_EDGE	G7_MOPPlus_V6		False	False	False	False	True			
AUTO	Bool	false	False	False	False	False	False			
MAN	Bool	false	False	False	False	False	False			
TAP	Bool	false	False	False	False	False	False			
TOP	Bool	false	False	False	False	False	False			
ACK_S	Bool	false	False	False	False	False	False			
REG_S	Bool	false	False	False	False	False	False			
T_PREV	Bool	false	False	False	False	False	False			
T_NEXT	Bool	false	False	False	False	False	False			
LOCK	Bool	false	False	False	False	False	False			
SUP	Bool	false	False	False	False	False	False			
ACKREQ	Bool	false	False	False	False	False	False			
SSKIP	Bool	false	False	False	False	False	False			
OFF	Bool	false	False	False	False	False	False			
INIT	Bool	false	False	False	False	False	False			
HALT	Bool	false	False	False	False	False	False			
TMS_HALT	Bool	false	False	False	False	False	False			
OPS_ZERO	Bool	false	False	False	False	False	False			
SACT_DISP	Bool	false	False	False	False	False	False			
SEF_DISP	Bool	false	False	False	False	False	False			
SALL_DISP	Bool	false	False	False	False	False	False			
S_PREV	Bool	false	False	False	False	False	False			
S_NEXT	Bool	false	False	False	False	False	False			
S_SELOK	Bool	false	False	False	False	False	False			
S_ON	Bool	false	False	False	False	False	False			
S_OFF	Bool	false	False	False	False	False	False			
T_PUSH	Bool	false	False	False	False	False	False			
REG	Bool	false	False	False	False	False	False			
ACK	Bool	false	False	False	False	False	False			
IL_PERM	Bool	false	False	False	False	False	False			
T_PERM	Bool	false	False	False	False	False	False			
ILP_MAN	Bool	false	False	False	False	False	False			
LMODE	Bool	false	False	False	False	False	False			
RESET_CRIT	Bool	false	False	False	False	False	False			
▼ MOP	G7_MOPPlus_V6		False	False	False	False	True			
AUTO	Bool	true	False	False	False	False	False			
MAN	Bool	false	False	False	False	False	False			
TAP	Bool	false	False	False	False	False	False			
TOP	Bool	false	False	False	False	False	False			
ACK_S	Bool	false	False	False	False	False	False			
REG_S	Bool	false	False	False	False	False	False			
T_PREV	Bool	false	False	False	False	False	False			
T_NEXT	Bool	false	False	False	False	False	False			
LOCK	Bool	true	False	False	False	False	False			
SUP	Bool	true	False	False	False	False	False			
ACKREQ	Bool	true	False	False	False	False	False			
SSKIP	Bool	false	False	False	False	False	False			
OFF	Bool	false	False	False	False	False	False			
INIT	Bool	true	False	False	False	False	False			
HALT	Bool	false	False	False	False	False	False			
TMS_HALT	Bool	false	False	False	False	False	False			
OPS_ZERO	Bool	false	False	False	False	False	False			
SACT_DISP	Bool	true	False	False	False	False	False			
SEF_DISP	Bool	false	False	False	False	False	False			
SALL_DISP	Bool	false	False	False	False	False	False			
S_PREV	Bool	false	False	False	False	False	False			
S_NEXT	Bool	false	False	False	False	False	False			
S_SELOK	Bool	false	False	False	False	False	False			
S_ON	Bool	false	False	False	False	False	False			
S_OFF	Bool	false	False	False	False	False	False			
T_PUSH	Bool	false	False	False	False	False	False			
REG	Bool	false	False	False	False	False	False			
ACK	Bool	false	False	False	False	False	False			
IL_PERM	Bool	false	False	False	False	False	False			
T_PERM	Bool	false	False	False	False	False	False			
ILP_MAN	Bool	false	False	False	False	False	False			

Totally Integrated Automation Portal										
Name		Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
EXEC_BITS[189]		Bool	false	False	False	False	False	False		
EXEC_BITS[190]		Bool	false	False	False	False	False	False		
EXEC_BITS[191]		Bool	false	False	False	False	False	False		
EXEC_BITS[192]		Bool	false	False	False	False	False	False		
EXEC_BITS[193]		Bool	false	False	False	False	False	False		
EXEC_BITS[194]		Bool	false	False	False	False	False	False		
EXEC_BITS[195]		Bool	false	False	False	False	False	False		
EXEC_BITS[196]		Bool	false	False	False	False	False	False		
EXEC_BITS[197]		Bool	false	False	False	False	False	False		
EXEC_BITS[198]		Bool	false	False	False	False	False	False		
EXEC_BITS[199]		Bool	false	False	False	False	False	False		
EXEC_BITS[200]		Bool	false	False	False	False	False	False		
EXEC_BITS[201]		Bool	false	False	False	False	False	False		
EXEC_BITS[202]		Bool	false	False	False	False	False	False		
EXEC_BITS[203]		Bool	false	False	False	False	False	False		
EXEC_BITS[204]		Bool	false	False	False	False	False	False		
EXEC_BITS[205]		Bool	false	False	False	False	False	False		
EXEC_BITS[206]		Bool	false	False	False	False	False	False		
EXEC_BITS[207]		Bool	false	False	False	False	False	False		
EXEC_BITS[208]		Bool	false	False	False	False	False	False		
EXEC_BITS[209]		Bool	false	False	False	False	False	False		
EXEC_BITS[210]		Bool	false	False	False	False	False	False		
EXEC_BITS[211]		Bool	false	False	False	False	False	False		
EXEC_BITS[212]		Bool	false	False	False	False	False	False		
EXEC_BITS[213]		Bool	false	False	False	False	False	False		
EXEC_BITS[214]		Bool	false	False	False	False	False	False		
EXEC_BITS[215]		Bool	false	False	False	False	False	False		
EXEC_BITS[216]		Bool	false	False	False	False	False	False		
EXEC_BITS[217]		Bool	false	False	False	False	False	False		
EXEC_BITS[218]		Bool	false	False	False	False	False	False		
EXEC_BITS[219]		Bool	false	False	False	False	False	False		
EXEC_BITS[220]		Bool	false	False	False	False	False	False		
EXEC_BITS[221]		Bool	false	False	False	False	False	False		
EXEC_BITS[222]		Bool	false	False	False	False	False	False		
EXEC_BITS[223]		Bool	false	False	False	False	False	False		
EXEC_BITS[224]		Bool	false	False	False	False	False	False		
EXEC_BITS[225]		Bool	false	False	False	False	False	False		
EXEC_BITS[226]		Bool	false	False	False	False	False	False		
EXEC_BITS[227]		Bool	false	False	False	False	False	False		
EXEC_BITS[228]		Bool	false	False	False	False	False	False		
EXEC_BITS[229]		Bool	false	False	False	False	False	False		
EXEC_BITS[230]		Bool	false	False	False	False	False	False		
EXEC_BITS[231]		Bool	false	False	False	False	False	False		
EXEC_BITS[232]		Bool	false	False	False	False	False	False		
EXEC_BITS[233]		Bool	false	False	False	False	False	False		
EXEC_BITS[234]		Bool	false	False	False	False	False	False		
EXEC_BITS[235]		Bool	false	False	False	False	False	False		
EXEC_BITS[236]		Bool	false	False	False	False	False	False		
EXEC_BITS[237]		Bool	false	False	False	False	False	False		
EXEC_BITS[238]		Bool	false	False	False	False	False	False		
EXEC_BITS[239]		Bool	false	False	False	False	False	False		
EXEC_BITS[240]		Bool	false	False	False	False	False	False		
EXEC_BITS[241]		Bool	false	False	False	False	False	False		
EXEC_BITS[242]		Bool	false	False	False	False	False	False		
EXEC_BITS[243]		Bool	false	False	False	False	False	False		
EXEC_BITS[244]		Bool	false	False	False	False	False	False		
EXEC_BITS[245]		Bool	false	False	False	False	False	False		
EXEC_BITS[246]		Bool	false	False	False	False	False	False		
EXEC_BITS[247]		Bool	false	False	False	False	False	False		
EXEC_BITS[248]		Bool	false	False	False	False	False	False		
EXEC_BITS[249]		Bool	false	False	False	False	False	False		
▼ OFFSETS		G7_Offsets-Plus_V6		False	False	False	False	True		
SINI_OFFSET		UInt	0	False	False	False	False	False		
LSTT_OFFSET		UInt	16	False	False	False	False	False		
ATAJ_OFFSET		UInt	28	False	False	False	False	False		
ATAB_OFFSET		UInt	40	False	False	False	False	False		
PSTT_OFFSET		UInt	52	False	False	False	False	False		
NSTT_OFFSET		UInt	64	False	False	False	False	False		
ASSJ_OFFSET		UInt	76	False	False	False	False	False		
ASSB_OFFSET		UInt	94	False	False	False	False	False		
PTTS_OFFSET		UInt	112	False	False	False	False	False		
NTTS_OFFSET		UInt	130	False	False	False	False	False		

Totally Integrated Automation Portal										
Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment	
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	1	False	False	False	False	False			
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			
▼ Fill NaOH	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	2	False	False	False	False	False			
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			
▼ Fill Powder M001	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	3	False	False	False	False	False			
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			

Totally Integrated Automation Portal										
Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment	
▼ Start Mixing	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	4	False	False	False	False	False			
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			
▼ Empty MIX Tank	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	5	False	False	False	False	False			
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			
▼ Stop Water	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	6	False	False	False	False	False			

Totally Integrated Automation Portal										
Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment	
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			
▼ Close NaOH valve	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	7	False	False	False	False	False			
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			
▼ Powder Motor Stop	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	8	False	False	False	False	False			
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			
▼ Stop Mixing	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			

Totally Integrated Automation Portal										
Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment	
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	9	False	False	False	False	False			
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			
▼ Empty Storage Tank	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	10	False	False	False	False	False			
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			
▼ Stop emptying	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	11	False	False	False	False	False			
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			

Totally Integrated Automation Portal									
Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Exit valve open	G7_StepPlus_V6		False	False	False	False	True		Step structure
S1	Bool	false	False	False	False	False	False		
L1	Bool	false	False	False	False	False	False		
V1	Bool	false	False	False	False	False	False		
R1	Bool	false	False	False	False	False	False		
A1	Bool	false	False	False	False	False	False		
S0	Bool	false	False	False	False	False	False		
L0	Bool	false	False	False	False	False	False		
V0	Bool	false	False	False	False	False	False		
X	Bool	false	False	False	False	False	False		
LA	Bool	false	False	False	False	False	False		
VA	Bool	false	False	False	False	False	False		
RA	Bool	false	False	False	False	False	False		
AA	Bool	false	False	False	False	False	False		
SS	Bool	false	False	False	False	False	False		
LS	Bool	true	False	False	False	False	False		
VS	Bool	false	False	False	False	False	False		
SNO	Int	12	False	False	False	False	False		
T	Time	T#0ms	False	False	False	False	False		
U	Time	T#0ms	False	False	False	False	False		
T_MAX	Time	T#10S	False	False	False	False	False		
T_WARN	Time	T#7S	False	False	False	False	False		
CRIT_LOC	DWord	16#0	False	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False		
SM	Bool	false	False	False	False	False	False		
H_IL_ERR	Byte	16#0	False	False	False	False	False		
H_SV_FLT	Byte	16#04	False	False	False	False	False		
▼ Step13	G7_StepPlus_V6		False	False	False	False	True		Step structure
S1	Bool	false	False	False	False	False	False		
L1	Bool	false	False	False	False	False	False		
V1	Bool	false	False	False	False	False	False		
R1	Bool	false	False	False	False	False	False		
A1	Bool	false	False	False	False	False	False		
S0	Bool	false	False	False	False	False	False		
L0	Bool	false	False	False	False	False	False		
V0	Bool	false	False	False	False	False	False		
X	Bool	false	False	False	False	False	False		
LA	Bool	false	False	False	False	False	False		
VA	Bool	false	False	False	False	False	False		
RA	Bool	false	False	False	False	False	False		
AA	Bool	false	False	False	False	False	False		
SS	Bool	false	False	False	False	False	False		
LS	Bool	true	False	False	False	False	False		
VS	Bool	false	False	False	False	False	False		
SNO	Int	13	False	False	False	False	False		
T	Time	T#0ms	False	False	False	False	False		
U	Time	T#0ms	False	False	False	False	False		
T_MAX	Time	T#10S	False	False	False	False	False		
T_WARN	Time	T#7S	False	False	False	False	False		
CRIT_LOC	DWord	16#0	False	False	False	False	False		
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False		
SM	Bool	false	False	False	False	False	False		
H_IL_ERR	Byte	16#0	False	False	False	False	False		
H_SV_FLT	Byte	16#04	False	False	False	False	False		
▼ Not to Storage	G7_StepPlus_V6		False	False	False	False	True		Step structure
S1	Bool	false	False	False	False	False	False		
L1	Bool	false	False	False	False	False	False		
V1	Bool	false	False	False	False	False	False		
R1	Bool	false	False	False	False	False	False		
A1	Bool	false	False	False	False	False	False		
S0	Bool	false	False	False	False	False	False		
L0	Bool	false	False	False	False	False	False		
V0	Bool	false	False	False	False	False	False		
X	Bool	false	False	False	False	False	False		
LA	Bool	false	False	False	False	False	False		
VA	Bool	false	False	False	False	False	False		
RA	Bool	false	False	False	False	False	False		
AA	Bool	false	False	False	False	False	False		
SS	Bool	false	False	False	False	False	False		
LS	Bool	true	False	False	False	False	False		
VS	Bool	false	False	False	False	False	False		
SNO	Int	14	False	False	False	False	False		

Totally Integrated Automation Portal										
Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment	
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			
▼ Exit valve close	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	15	False	False	False	False	False			
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			
▼ Valve 521 Stays open	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			
X	Bool	false	False	False	False	False	False			
LA	Bool	false	False	False	False	False	False			
VA	Bool	false	False	False	False	False	False			
RA	Bool	false	False	False	False	False	False			
AA	Bool	false	False	False	False	False	False			
SS	Bool	false	False	False	False	False	False			
LS	Bool	true	False	False	False	False	False			
VS	Bool	false	False	False	False	False	False			
SNO	Int	16	False	False	False	False	False			
T	Time	T#0ms	False	False	False	False	False			
U	Time	T#0ms	False	False	False	False	False			
T_MAX	Time	T#10S	False	False	False	False	False			
T_WARN	Time	T#7S	False	False	False	False	False			
CRIT_LOC	DWord	16#0	False	False	False	False	False			
CRIT_LOC_ERR	DWord	16#0	False	False	False	False	False			
SM	Bool	false	False	False	False	False	False			
H_IL_ERR	Byte	16#0	False	False	False	False	False			
H_SV_FLT	Byte	16#04	False	False	False	False	False			
▼ Fill water	G7_StepPlus_V6		False	False	False	False	True		Step structure	
S1	Bool	false	False	False	False	False	False			
L1	Bool	false	False	False	False	False	False			
V1	Bool	false	False	False	False	False	False			
R1	Bool	false	False	False	False	False	False			
A1	Bool	false	False	False	False	False	False			
S0	Bool	false	False	False	False	False	False			
L0	Bool	false	False	False	False	False	False			
V0	Bool	false	False	False	False	False	False			


ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks

FB_TestMode [FB9]

FB_TestMode Properties							
General							
Name	FB_TestMode	Number	9	Type	FB	Language	FBD
Numbering	Automatic						
Information							
Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
TestOn	Bool	false	Non-retain	True	True	True	False		Test mode enable
TestOff	Bool	false	Non-retain	True	True	True	False		
▼ Output									
Valve1	Bool	false	Non-retain	True	True	True	False		
Valve2	Bool	false	Non-retain	True	True	True	False		
Valve3	Bool	false	Non-retain	True	True	True	False		
Valve4	Bool	false	Non-retain	True	True	True	False		
Valve5	Bool	false	Non-retain	True	True	True	False		
Motor1	Bool	false	Non-retain	True	True	True	False		
Motor2	Bool	false	Non-retain	True	True	True	False		
Motor3	Bool	false	Non-retain	True	True	True	False		
InOut									
▼ Static									
TestRSmemory	Bool	false	Non-retain	True	True	True	False		
Temp									
Constant									

Network 1:



Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks

DB_TestMode [DB24]

DB_TestMode Properties

General

Name	DB_TestMode	Number	24	Type	DB	Language	DB
Numbering	Automatic						

Information

Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
TestOn	Bool	false	False	True	True	True	False		Test mode enable
TestOff	Bool	false	False	True	True	True	False		
▼ Output									
Valve1	Bool	false	False	True	True	True	False		
Valve2	Bool	false	False	True	True	True	False		
Valve3	Bool	false	False	True	True	True	False		
Valve4	Bool	false	False	True	True	True	False		
Valve5	Bool	false	False	True	True	True	False		
Motor1	Bool	false	False	True	True	True	False		
Motor2	Bool	false	False	True	True	True	False		
Motor3	Bool	false	False	True	True	True	False		
InOut									
▼ Static									
TestRSmemory	Bool	false	False	True	True	True	False		

Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / System blocks / Program resources

MixTankMotorTlmer [DB2]

MixTankMotorTlmer Properties

General

Name	MixTankMotorTlmer	Number	2	Type	DB	Language	DB
Numbering	Automatic						

Information

Title		Author	Simatic	Comment		Family	IEC
Version	1.0	User-defined ID	IEC_TMR				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Static									
PT	Time	T#0ms	False	True	True	True	False		
ET	Time	T#0ms	False	True	False	True	False		
IN	Bool	false	False	True	True	True	False		
Q	Bool	false	False	True	False	True	False		

Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Motors / Generic Motors

FC_Motor_Set [FC5]

FC_Motor_Set Properties

General

Name	FC_Motor_Set	Number	5	Type	FC	Language	FBD
Numbering	Automatic						

Information

Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Comment
▼ Input			
bStart_IFC	Bool		Start request for motor
▼ Output			
bSet_QFC	Bool		Set signal to motor memory
InOut			
Temp			
Constant			
▼ Return			
FC_Motor_Set	Void		

Network 1: Set signal to motor memory

#bSet_QFC

=

#bStart_IFC

Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Motors / Generic Motors

FC_Motor_Reset [FC6]

FC_Motor_Reset Properties

General

Name	FC_Motor_Reset	Number	6	Type	FC	Language	FBD
Numbering	Automatic						

Information

Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Comment
▼ Input			
bStop_IFC	Bool		Stop request for motor
▼ Output			
bReset_QFC	Bool		Reset signal to motor memory
InOut			
Temp			
Constant			
▼ Return			
FC_Motor_Reset	Void		

Network 1: Reset output

#bReset_QFC

#bStop_IFC

=


ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Motors / Generic Motors

FB_Motor [FB11]

FB_Motor Properties							
General							
Name	FB_Motor	Number	11	Type	FB	Language	FBD
Numbering	Automatic						
Information							
Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
bStart_IFB	Bool	false	Non-retain	True	True	True	False		
bStop_IFB	Bool	false	Non-retain	True	True	True	False		
▼ Output									
bST_QFB	Bool	false	Non-retain	True	True	True	False		
InOut									
Static									
▼ Temp									
Reset	Bool								
Set	Bool								
Constant									

Network 1:



ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Sensors / Generic Blocks


FC_Scale [FC2]

FC_Scale Properties							
General							
Name	FC_Scale	Number	2	Type	FC	Language	FBD
Numbering	Automatic						
Information							
Title	Scaling for Sensors	Author		Comment	This is a basic mechanism for scaling Sensors. For details about using Function scale, visit this website https://support.industry.siemens.com/cs/document/1765297/how-and-for-which-analog-measurements-can-you-use-the-function-fc105-scale-to-convert-the-integer-values-(int)-into-real-number-values?dti=0&lc=en-SZ	Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Comment
▼ Input			
RawValue	Int		Connect the sensor Straight here. 4-20mA = 0-27648 Integers.
HighLimitForSensor	Real		High limit required in plan
LowLimitForSensor	Real		Low limit required in plan
DoLimitsNegative	Bool		If limit is negative then Bipolar:= true elseif positive then unipolar:= true
▼ Output			
ActualOutput	Real		Usable output for futher use.
VisualOutput	Word		Visual Output for further use.
InOut			
Temp			
Constant			
▼ Return			
FC_Scale	Void		

Network 1:

Basci scale block



ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Sensors / Generic Blocks


SensorScaling [FB3]

SensorScaling Properties							
General							
Name	SensorScaling	Number	3	Type	FB	Language	FBD
Numbering	Automatic						
Information							
Title	Sensor Fb Block	Author		Comment	The idea is to call this from FC and then call it into OB and connect sensors individually, by doing that DB instance can be created for sensors and everythin will be connected inside one and highest layer, this will help in maintenance, monitoring, optimization, further analysis and future possibilities.	Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
RawValue	Int	0	Non-retain	False	False	False	False		Connect the sensor Straight here. 4-20mA = 0-27648 Integers.
HighLimitForSensor	Real	0.0	Non-retain	False	False	False	False		High limit required in plan
LowLimitForSensor	Real	0.0	Non-retain	False	False	False	False		Low limit required in plan
DoLimitsIsNegative	Bool	false	Non-retain	False	False	False	False		If limit is negative then Bipolar:= true elseif positive then unipolar:= true
▼ Output									
VisualOutput	Word	16#0	Non-retain	False	False	False	False		Visual Output for further use.
ScaledPercentage	Real	0.0	Non-retain	True	True	True	False		
InOut									
▼ Static									
Result	Real	0.0	Non-retain	True	True	True	False		
ActualOutput	Real	0.0	Non-retain	False	False	False	False		Usable output for futher use.
Temp									
Constant									

Network 1:

Basic FC to FB call.



Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Sensors / DataBlocks

DB_Sensor_LI_515 [DB15]

DB_Sensor_LI_515 Properties

General

Name	DB_Sensor_LI_515	Number	15	Type	DB	Language	DB
Numbering	Automatic						

Information

Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
RawValue	Int	0	False	False	False	False	False		Connect the sensor Straight here. 4-20mA = 0-27648 Integers.
HighLimitForSensor	Real	0.0	False	False	False	False	False		High limit required in plan
LowLimitForSensor	Real	0.0	False	False	False	False	False		Low limit required in plan
DoLimitsNegative	Bool	false	False	False	False	False	False		If limit is negative then Bipolar:= true elseif positive then unipolar:= true
▼ Output									
VisualOutput	Word	16#0	False	False	False	False	False		Visual Output for further use.
ScaledPercentage	Real	0.0	False	True	True	True	False		
InOut									
▼ Static									
Result	Real	0.0	False	True	True	True	False		
ActualOutput	Real	0.0	False	False	False	False	False		Usable output for futher use.

Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Sensors / DataBlocks

Db_Sensor_TI_517 [DB16]

Db_Sensor_TI_517 Properties

General

Name	Db_Sensor_TI_517	Number	16	Type	DB	Language	DB
Numbering	Automatic						

Information

Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
RawValue	Int	0	False	False	False	False	False		Connect the sensor Straight here. 4-20mA = 0-27648 Integers.
HighLimitForSensor	Real	0.0	False	False	False	False	False		High limit required in plan
LowLimitForSensor	Real	0.0	False	False	False	False	False		Low limit required in plan
DoLimitsNegative	Bool	false	False	False	False	False	False		If limit is negative then Bipolar:= true elseif positive then unipolar:= true
▼ Output									
VisualOutput	Word	16#0	False	False	False	False	False		Visual Output for further use.
ScaledPercentage	Real	0.0	False	True	True	True	False		
InOut									
▼ Static									
Result	Real	0.0	False	True	True	True	False		
ActualOutput	Real	0.0	False	False	False	False	False		Usable output for futher use.

Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Sensors / DataBlocks

DB_Sensor_TI_518 [DB17]

DB_Sensor_TI_518 Properties

General

Name	DB_Sensor_TI_518	Number	17	Type	DB	Language	DB
Numbering	Automatic						

Information

Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
RawValue	Int	0	False	False	False	False	False		Connect the sensor Straight here. 4-20mA = 0-27648 Integers.
HighLimitForSensor	Real	0.0	False	False	False	False	False		High limit required in plan
LowLimitForSensor	Real	0.0	False	False	False	False	False		Low limit required in plan
DoLimitsNegative	Bool	false	False	False	False	False	False		If limit is negative then Bipolar:= true elseif positive then unipolar:= true
▼ Output									
VisualOutput	Word	16#0	False	False	False	False	False		Visual Output for further use.
ScaledPercentage	Real	0.0	False	True	True	True	False		
InOut									
▼ Static									
Result	Real	0.0	False	True	True	True	False		
ActualOutput	Real	0.0	False	False	False	False	False		Usable output for futher use.

Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Sensors / DataBlocks

DB_Sensor_WI_512 [DB12]

DB_Sensor_WI_512 Properties

General

Name	DB_Sensor_WI_512	Number	12	Type	DB	Language	DB
Numbering	Automatic						

Information

Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
RawValue	Int	0	False	False	False	False	False		Connect the sensor Straight here. 4-20mA = 0-27648 Integers.
HighLimitForSensor	Real	0.0	False	False	False	False	False		High limit required in plan
LowLimitForSensor	Real	0.0	False	False	False	False	False		Low limit required in plan
DoLimitsNegative	Bool	false	False	False	False	False	False		If limit is negative then Bipolar:= true elseif positive then unipolar:= true
▼ Output									
VisualOutput	Word	16#0	False	False	False	False	False		Visual Output for further use.
ScaledPercentage	Real	0.0	False	True	True	True	False		
InOut									
▼ Static									
Result	Real	0.0	False	True	True	True	False		
ActualOutput	Real	0.0	False	False	False	False	False		Usable output for futher use.

Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Sensors / DataBlocks

DB_Sensor_FIC_516 [DB4]

DB_Sensor_FIC_516 Properties

General

Name	DB_Sensor_FIC_516	Number	4	Type	DB	Language	DB
Numbering	Automatic						

Information

Title		Author		Comment		Family	
Version	0.1	User-defined ID					


Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
RawValue	Int	0	False	False	False	False	False		Connect the sensor Straight here. 4-20mA = 0-27648 Integers.
HighLimitForSensor	Real	0.0	False	False	False	False	False		High limit required in plan
LowLimitForSensor	Real	0.0	False	False	False	False	False		Low limit required in plan
DoLimitsNegative	Bool	false	False	False	False	False	False		If limit is negative then Bipolar:= true elseif positive then unipolar:= true
▼ Output									
VisualOutput	Word	16#0	False	False	False	False	False		Visual Output for further use.
ScaledPercentage	Real	0.0	False	True	True	True	False		
InOut									
▼ Static									
Result	Real	0.0	False	True	True	True	False		
ActualOutput	Real	0.0	False	False	False	False	False		Usable output for futher use.

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Valves / Generic valves

Valves [FC1]

Valves Properties							
General							
Name	Valves	Number	1	Type	FC	Language	FBD
Numbering	Automatic						
Information							
Title		Author		Comment		Family	
Version	0.1	User-defined ID					
Name		Data type	Default value		Comment		
▼ Input							
bSet_IFC		Bool			Set valve open command		
bReset_IFC		Bool			Reset valve close command		
▼ Output							
bSet_QFC		Bool			Set signal to valve memory		
bReset_QFC		Bool			Reset signal to valve memory		
InOut							
Temp							
Constant							
▼ Return							
Valves		Void					

Network 1: Set signal to valve memory




ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Valves / Generic valves

FB_Valve [FB2]

FB_Valve Properties							
General							
Name	FB_Valve	Number	2	Type	FB	Language	FBD
Numbering	Automatic						
Information							
Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
SetIn	Bool	false	Non-retain	True	True	True	False		
ResetIn	Bool	false	Non-retain	True	True	True	False		
▼ Output									
Valve	Bool	false	Non-retain	True	True	True	False		
InOut									
Static									
▼ Temp									
SetOutput	Bool								
ResetOutput	Bool								
Constant									

Network 1:



DB_GSV_511 [DB6]

General							
Name	DB_GSV_511	Number	6	Type	DB	Language	DB
Numbering	Automatic						
Information							
Title		Author		Comment		Family	
Version	0.1	User-defined ID					

[illegible]

DB_GSV_514 [DB7]

DB_GSV_514 Properties							
General							
Name	DB_GSV_514	Number	7	Type	DB	Language	DB
Numbering	Automatic						
Information							
Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
SetIn	Bool	false	False	True	True	True	False		
ResetIn	Bool	false	False	True	True	True	False		
▼ Output									
Valve	Bool	false	False	True	True	True	False		
InOut									
Static									

DB_HMI [DB19]

DB_HMI Properties							
General							
Name	DB_HMI	Number	19	Type	DB	Language	DB
Numbering	Automatic						
Information							
Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
bStartButton	Bool	false	False	True	True	True	False		
bStopButton	Bool	false	False	True	True	True	False		
bResetButton	Bool	false	False	True	True	True	False		
bAutoSelected	Bool	false	False	True	True	True	False		
bManualSelected	Bool	false	False	True	True	True	False		
▼ Output									
bStartCmd	Bool	false	False	True	True	True	False		
bStopCmd	Bool	false	False	True	True	True	False		
bResetCmd	Bool	false	False	True	True	True	False		
bAutoMode	Bool	false	False	True	True	True	False		
bManualMode	Bool	false	False	True	True	True	False		
InOut									
Static									

Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Process / Data Blocks

DB_Fault [DB23]

DB_Fault Properties

General

Name	DB_Fault	Number	23	Type	DB	Language	DB
Numbering	Automatic						

Information

Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
bEStopActive	Bool	false	False	True	True	True	False		
bSensorFault	Bool	false	False	True	True	True	False		
bDeviceFault	Bool	false	False	True	True	True	False		
bReset	Bool	false	False	True	True	True	False		
▼ Output									
bFaultActive	Bool	false	False	True	True	True	False		
InOut									
Static									

DB_Stop [DB22]

DB_Stop Properties							
General							
Name	DB_Stop	Number	22	Type	DB	Language	DB
Numbering	Automatic						
Information							
Title		Author		Comment		Family	
Version	0.1	User-defined ID					

[illegible]


ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Process / Process FBs

FB_Auto [FB4]

FB_Auto Properties							
General							
Name	FB_Auto	Number	4	Type	FB	Language	FBD
Numbering	Automatic						
Information							
Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
bAutoSelected	Bool	false	Non-retain	True	True	True	False		
bStart	Bool	false	Non-retain	True	True	True	False		
bStop	Bool	false	Non-retain	True	True	True	False		
▼ Output									
bAutoEnable	Bool	false	Non-retain	True	True	True	False		
InOut									
Static									
Temp									
Constant									

Network 1:



ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Process / Process FBs

FB_EStop [FB6]

FB_EStop Properties							
General							
Name	FB_EStop	Number	6	Type	FB	Language	FBD
Numbering	Automatic						
Information							
Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
bEStopInput	Bool	false	Non-retain	True	True	True	False		
▼ Output									
bEStopActive	Bool	false	Non-retain	True	True	True	False		
InOut									
Static									
Temp									
Constant									

Network 1:




ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Process / Process FBs

FB_Fault [FB7]

FB_Fault Properties							
General							
Name	FB_Fault	Number	7	Type	FB	Language	FBD
Numbering	Automatic						
Information							
Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
bEStopActive	Bool	false	Non-retain	True	True	True	False		
bSensorFault	Bool	false	Non-retain	True	True	True	False		
bDeviceFault	Bool	false	Non-retain	True	True	True	False		
bReset	Bool	false	Non-retain	True	True	True	False		
▼ Output									
bFaultActive	Bool	false	Non-retain	True	True	True	False		
InOut									
Static									
Temp									
Constant									

Network 1:




ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Program blocks / Process / Process FBs

FB_Manual [FB5]

FB_Manual Properties							
General							
Name	FB_Manual	Number	5	Type	FB	Language	FBD
Numbering	Automatic						
Information							
Title		Author		Comment		Family	
Version	0.1	User-defined ID					

Name	Data type	Default value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
bManualSelected	Bool	false	Non-retain	True	True	True	False		
bStop	Bool	false	Non-retain	True	True	True	False		
▼ Output									
bManualEnable	Bool	false	Non-retain	True	True	True	False		
InOut									
Static									
Temp									
Constant									

Network 1:



Totally Integrated Automation Portal									
ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Technology objects									
DB_PID_Compact [DB11]									
DB_PID_Compact Properties									
General									
Name	DB_PID_Compact	Number	11	Type	DB	Language	DB		
Numbering	Automatic								
Information									
Title		Author	SIMATIC	Comment		Family	COMPPID		
Version	2.4	User-defined ID	PID_Cmpt						
Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Setpoint	Real	0.0	False	True	True	True	False		
Input	Real	0.0	False	True	True	True	False		
Input_PER	Int	0	False	True	True	True	False		
Disturbance	Real	0.0	False	True	True	True	False		
ManualEnable	Bool	false	False	True	True	True	False		
ManualValue	Real	0.0	False	True	True	True	False		
ErrorAck	Bool	false	False	True	True	True	False		
Reset	Bool	false	False	True	True	True	False		
ModeActivate	Bool	false	False	True	True	True	False		
▼ Output									
ScaledInput	Real	0.0	False	True	False	True	False		
Output	Real	0.0	False	True	False	True	False		
Output_PER	Int	0	False	True	False	True	False		
Output_PWM	Bool	false	False	True	False	True	False		
SetpointLimit_H	Bool	false	False	True	False	True	False		
SetpointLimit_L	Bool	false	False	True	False	True	False		
InputWarning_H	Bool	false	False	True	False	True	False		
InputWarning_L	Bool	false	False	True	False	True	False		
State	Int	0	False	True	False	True	False		
Error	Bool	false	False	True	False	True	False		
ErrorBits	DWord	16#0	True	True	False	True	False		
▼ InOut									
Mode	Int	4	True	True	True	True	False		
▼ Static									
InternalDiagnostic	DWord	0	False	False	False	False	False		
InternalVersion	DWord	DW#16#02040001	False	True	False	True	False		
InternalRTVersion	DWord	0	False	False	False	False	False		
IntegralResetMode	Int	4	False	True	True	True	True		
OverwriteInitialOutputValue	Real	0.0	False	True	True	True	False		
RunModeByStartup	Bool	true	False	True	True	True	True		
LoadBackUp	Bool	false	False	True	True	True	False		
SetSubstituteOutput	Bool	true	False	True	True	True	True		
PhysicalUnit	Int	0	False	True	False	True	True		
PhysicalQuantity	Int	0	False	True	False	True	True		
ActivateRecoverMode	Bool	true	False	True	True	True	True		
Warning	DWord	16#0	True	True	False	True	False		
WarningInternal	DWord	16#0	True	True	False	True	False		
Progress	Real	0.0	False	True	False	True	False		
CurrentSetpoint	Real	0.0	False	True	False	True	False		
CancelTuningLevel	Real	10.0	False	True	True	True	True		
SubstituteOutput	Real	0.0	False	True	True	True	True		
▼ Config	PID_Compact-Config		False	True	True	True	True		
InputPerOn	Bool	true	False	True	True	True	True		
InvertControl	Bool	false	False	True	True	True	True		
InputUpperLimit	Real	120.0	False	True	True	True	True		
InputLowerLimit	Real	0.0	False	True	True	True	True		
InputUpperWarning	Real	3.402822e+38	False	True	True	True	True		
InputLowerWarning	Real	-3.402822e+38	False	True	True	True	True		
OutputUpperLimit	Real	100.0	False	True	True	True	True		
OutputLowerLimit	Real	0.0	False	True	True	True	True		
SetpointUpperLimit	Real	3.402822e+38	False	True	True	True	True		
SetpointLowerLimit	Real	-3.402822e+38	False	True	True	True	True		
MinimumOnTime	Real	0.0	False	True	True	True	True		
MinimumOffTime	Real	0.0	False	True	True	True	True		
▼ InputScaling	PID_Scaling		False	True	True	True	True		
UpperPointIn	Real	27648.0	False	True	True	True	True		
LowerPointIn	Real	0.0	False	True	True	True	True		
UpperPointOut	Real	100.0	False	True	True	True	True		

Totally Integrated Automation Portal									
ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Technology objects									
PID_Compact_1 [DB1]									
PID_Compact_1 Properties									
General									
Name	PID_Compact_1	Number	1	Type	DB	Language	DB		
Numbering	Automatic								
Information									
Title		Author	SIMATIC	Comment		Family	COMPPID		
Version	2.4	User-defined ID	PID_Cmpt						
Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Setpoint	Real	0.0	False	True	True	True	False		
Input	Real	0.0	False	True	True	True	False		
Input_PER	Int	0	False	True	True	True	False		
Disturbance	Real	0.0	False	True	True	True	False		
ManualEnable	Bool	false	False	True	True	True	False		
ManualValue	Real	0.0	False	True	True	True	False		
ErrorAck	Bool	false	False	True	True	True	False		
Reset	Bool	false	False	True	True	True	False		
ModeActivate	Bool	false	False	True	True	True	False		
▼ Output									
ScaledInput	Real	0.0	False	True	False	True	False		
Output	Real	0.0	False	True	False	True	False		
Output_PER	Int	0	False	True	False	True	False		
Output_PWM	Bool	false	False	True	False	True	False		
SetpointLimit_H	Bool	false	False	True	False	True	False		
SetpointLimit_L	Bool	false	False	True	False	True	False		
InputWarning_H	Bool	false	False	True	False	True	False		
InputWarning_L	Bool	false	False	True	False	True	False		
State	Int	0	False	True	False	True	False		
Error	Bool	false	False	True	False	True	False		
ErrorBits	DWord	16#0	True	True	False	True	False		
▼ InOut									
Mode	Int	4	True	True	True	True	False		
▼ Static									
InternalDiagnostic	DWord	0	False	False	False	False	False		
InternalVersion	DWord	DW#16#02040001	False	True	False	True	False		
InternalRTVersion	DWord	0	False	False	False	False	False		
IntegralResetMode	Int	4	False	True	True	True	True		
OverwriteInitialOutputValue	Real	0.0	False	True	True	True	False		
RunModeByStartup	Bool	true	False	True	True	True	True		
LoadBackUp	Bool	false	False	True	True	True	False		
SetSubstituteOutput	Bool	true	False	True	True	True	True		
PhysicalUnit	Int	0	False	True	False	True	True		
PhysicalQuantity	Int	0	False	True	False	True	True		
ActivateRecoverMode	Bool	true	False	True	True	True	True		
Warning	DWord	16#0	True	True	False	True	False		
WarningInternal	DWord	16#0	True	True	False	True	False		
Progress	Real	0.0	False	True	False	True	False		
CurrentSetpoint	Real	0.0	False	True	False	True	False		
CancelTuningLevel	Real	10.0	False	True	True	True	True		
SubstituteOutput	Real	0.0	False	True	True	True	True		
▼ Config	PID_Compact-Config		False	True	True	True	True		
InputPerOn	Bool	true	False	True	True	True	True		
InvertControl	Bool	false	False	True	True	True	True		
InputUpperLimit	Real	120.0	False	True	True	True	True		
InputLowerLimit	Real	0.0	False	True	True	True	True		
InputUpperWarning	Real	3.402822e+38	False	True	True	True	True		
InputLowerWarning	Real	-3.402822e+38	False	True	True	True	True		
OutputUpperLimit	Real	100.0	False	True	True	True	True		
OutputLowerLimit	Real	0.0	False	True	True	True	True		
SetpointUpperLimit	Real	3.402822e+38	False	True	True	True	True		
SetpointLowerLimit	Real	-3.402822e+38	False	True	True	True	True		
MinimumOnTime	Real	0.0	False	True	True	True	True		
MinimumOffTime	Real	0.0	False	True	True	True	True		
▼ InputScaling	PID_Scaling		False	True	True	True	True		
UpperPointIn	Real	27648.0	False	True	True	True	True		
LowerPointIn	Real	0.0	False	True	True	True	True		
UpperPointOut	Real	100.0	False	True	True	True	True		

Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Technology objects

PID_M003 [DB13]

PID_M003 Properties

General

Name	PID_M003	Number	13	Type	DB	Language	DB
Numbering	Automatic						

Information

Title		Author	SIMATIC	Comment		Family	COMPPID
Version	2.4	User-defined ID	PID_Cmpt				

Name	Data type	Start value	Retain	Accessible from HMI/OPC UA/Web API	Writ-able from HMI/ OPC UA/ Web API	Visible in HMI engi-neering	Setpoint	Supervi-sion	Comment
▼ Input									
Setpoint	Real	0.0	False	True	True	True	False		
Input	Real	0.0	False	True	True	True	False		
Input_PER	Int	0	False	True	True	True	False		
Disturbance	Real	0.0	False	True	True	True	False		
ManualEnable	Bool	false	False	True	True	True	False		
ManualValue	Real	0.0	False	True	True	True	False		
ErrorAck	Bool	false	False	True	True	True	False		
Reset	Bool	false	False	True	True	True	False		
ModeActivate	Bool	false	False	True	True	True	False		
▼ Output									
ScaledInput	Real	0.0	False	True	False	True	False		
Output	Real	0.0	False	True	False	True	False		
Output_PER	Int	0	False	True	False	True	False		
Output_PWM	Bool	false	False	True	False	True	False		
SetpointLimit_H	Bool	false	False	True	False	True	False		
SetpointLimit_L	Bool	false	False	True	False	True	False		
InputWarning_H	Bool	false	False	True	False	True	False		
InputWarning_L	Bool	false	False	True	False	True	False		
State	Int	0	False	True	False	True	False		
Error	Bool	false	False	True	False	True	False		
ErrorBits	DWord	16#0	True	True	False	True	False		
▼ InOut									
Mode	Int	3	True	True	True	True	False		
▼ Static									
InternalDiagnostic	DWord	0	False	False	False	False	False		
InternalVersion	DWord	DW#16#02040001	False	True	False	True	False		
InternalRTVersion	DWord	0	False	False	False	False	False		
IntegralResetMode	Int	4	False	True	True	True	True		
OverwriteInitialOutputValue	Real	0.0	False	True	True	True	False		
RunModeByStartup	Bool	true	False	True	True	True	True		
LoadBackUp	Bool	false	False	True	True	True	False		
SetSubstituteOutput	Bool	true	False	True	True	True	True		
PhysicalUnit	Int	0	False	True	False	True	True		
PhysicalQuantity	Int	4	False	True	False	True	True		
ActivateRecoverMode	Bool	true	False	True	True	True	True		
Warning	DWord	16#0	True	True	False	True	False		
WarningInternal	DWord	16#0	True	True	False	True	False		
Progress	Real	0.0	False	True	False	True	False		
CurrentSetpoint	Real	0.0	False	True	False	True	False		
CancelTuningLevel	Real	10.0	False	True	True	True	True		
SubstituteOutput	Real	0.0	False	True	True	True	True		
▼ Config	PID_Compact-Config		False	True	True	True	True		
InputPerOn	Bool	FALSE	False	True	True	True	True		
InvertControl	Bool	false	False	True	True	True	True		
InputUpperLimit	Real	2.5	False	True	True	True	True		
InputLowerLimit	Real	0.0	False	True	True	True	True		
InputUpperWarning	Real	3.402822e+38	False	True	True	True	True		
InputLowerWarning	Real	-3.402822e+38	False	True	True	True	True		
OutputUpperLimit	Real	100.0	False	True	True	True	True		
OutputLowerLimit	Real	0.0	False	True	True	True	True		
SetpointUpperLimit	Real	3.402822e+38	False	True	True	True	True		
SetpointLowerLimit	Real	-3.402822e+38	False	True	True	True	True		
MinimumOnTime	Real	0.0	False	True	True	True	True		
MinimumOffTime	Real	0.0	False	True	True	True	True		
▼ InputScaling	PID_Scaling		False	True	True	True	True		
UpperPointIn	Real	27648.0	False	True	True	True	True		
LowerPointIn	Real	0.0	False	True	True	True	True		
UpperPointOut	Real	100.0	False	True	True	True	True		

Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / PLC tags / Default tag table [55]

PLC tags

PLC tags									
	Name	Data type	Address	Retain	Accessi-ble from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engi-neering	Supervision	Comment
	Start	Bool	%I12.0	False	True	True	True		
	Stop	Bool	%I12.1	False	True	True	True		
	FICSetpoint	Real	%MD14	False	True	True	True		

User constants

User constants				
	Name	Data type	Value	Comment

PLC tags

PLC tags									
	Name	Data type	Address	Retain	Accessi- ble from HMI/OPC UA/Web API	Writable from HMI/OPC UA/Web API	Visible in HMI engi- neering	Supervision	Comment
	ZSO-510	Bool	%I0.0	False	True	True	True		
	ZSC-510	Bool	%I0.1	False	True	True	True		
	ZSO-511	Bool	%I0.2	False	True	True	True		
	ZSC-511	Bool	%I0.3	False	True	True	True		
	ZSO-514	Bool	%I0.4	False	True	True	True		
	ZSC-514	Bool	%I0.5	False	True	True	True		
	ZSO-519	Bool	%I0.6	False	True	True	True		
	ZSC-519	Bool	%I0.7	False	True	True	True		
	ZSO-521	Bool	%I1.0	False	True	True	True		
	ZSC-521	Bool	%I1.1	False	True	True	True		
	M001.R	Bool	%I1.2	False	True	True	True		
	M002.R	Bool	%I1.3	False	True	True	True		
	LS-513	Bool	%I1.4	False	True	True	True		
	GSV-510	Bool	%Q0.0	False	True	True	True		
	GSV-511	Bool	%Q0.1	False	True	True	True		
	GSV-514	Bool	%Q0.2	False	True	True	True		
	GSV-519	Bool	%Q0.3	False	True	True	True		
	GSV-521	Bool	%Q0.4	False	True	True	True		
	M001.ST	Bool	%Q0.5	False	True	True	True		
	M002.ST	Bool	%Q0.6	False	True	True	True		
	WT-512	Int	%IW2	False	True	True	True		
	LT-515	Int	%IW4	False	True	True	True		
	FT-516	Int	%IW6	False	True	True	True		
	TT-517	Int	%IW8	False	True	True	True		
	TT-518	Int	%IW10	False	True	True	True		
	M003.SP	Int	%QW2	False	True	True	True		
	M001.F	Bool	%I1.5	False	True	True	True		
	M002.F	Bool	%I1.6	False	True	True	True		
	M003.R	Bool	%I1.7	False	True	True	True		
	M003.F	Bool	%I18.0	False	True	True	True		
	M003.ST	Bool	%Q0.7	False	True	True	True		
	M001.TK	Bool	%I18.1	False	True	True	True		
	M002.TK	Bool	%I18.2	False	True	True	True		
	M003.TK	Bool	%I18.3	False	True	True	True		

User constants

User constants				
	Name	Data type	Value	Comment

Totally Integrated Automation Portal		
ChemicalProcess / PLC_1 [CPU 1511-1 PN] / PLC data types System data types This folder is empty.		

Totally Integrated Automation Portal												
ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Watch and force tables Force table <table><tr><th>Name</th><th>Address</th><th>Display format</th><th>Force value</th><th>Comment</th></tr><tr><td colspan="5"></td></tr></table>			Name	Address	Display format	Force value	Comment					
Name	Address	Display format	Force value	Comment								

Totally Integrated Automation Portal		
ChemicalProcess / PLC_1 [CPU 1511-1 PN] Traces Name		

Totally Integrated Automation Portal		
ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Traces Measurements This folder is empty.		

Totally Integrated Automation Portal		
ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Traces Combined measurements Name		

Totally Integrated Automation Portal		
ChemicalProcess / PLC_1 [CPU 1511-1 PN] / OPC UA communication Server interfaces This folder is empty.		

Totally Integrated Automation Portal		
ChemicalProcess / PLC_1 [CPU 1511-1 PN] / OPC UA communication Client interfaces This folder is empty.		

Totally Integrated Automation Portal		
ChemicalProcess / PLC_1 [CPU 1511-1 PN] / PLC supervisions & alarms Supervisions This folder is empty.		

Totally Integrated Automation Portal					
ChemicalProcess / PLC_1 [CPU 1511-1 PN] / PLC supervisions & alarms					
PLC alarms					
PLC alarms					
Name	 IL_ALARM_INST	Type	PLC alarm	ID	
Location	ProcessSequence	Alarm text	Category : Supervision type : PLC name : FB name : Step name : Step number : Step specific field	Info text	
Alarm class	No Acknowledgement	Acknowledgment	False	Information only	False
Priority	0	Display class	0	Report	False
Created by	GRAPH	Date created	5/9/2026 9:57 PM	Last change	5/9/2026 9:57 PM
Group ID	0	Additional text 1		Additional text 2	
Additional text 3		Additional text 4		Additional text 5	
Additional text 6		Additional text 7		Additional text 8	
Additional text 9					
Name	 IL_ALARM_INST	Type	PLC alarm	ID	53
Location	ProcessSequence_DB	Alarm text	@2%t#SYSTEM_Global_ProDiag_SupervisionCategories@ : @2%t#SYSTEM_Global_ProDiag_Supervision-Types@ : \$\$CpuName\$\$: ProcessSequence : @1%t#SYSTEM_Step-Names639139229409982114_1@ : S@1%03d@ : @1%t#SYSTEM_InterlockAlarm-Texts639139229410127278_1@	Info text	
Alarm class	No Acknowledgement	Acknowledgment	False	Information only	False
Priority	0	Display class	0	Report	False
Created by	GRAPH	Date created	5/9/2026 9:57 PM	Last change	5/10/2026 1:33 PM
Group ID	0	Additional text 1		Additional text 2	
Additional text 3		Additional text 4		Additional text 5	
Additional text 6		Additional text 7		Additional text 8	
Additional text 9					
Name	 STEP_TIME_ALARM_INST	Type	PLC alarm	ID	
Location	ProcessSequence	Alarm text	Category : Supervision type : PLC name : FB name : Step name : Step number : Step specific field	Info text	
Alarm class	No Acknowledgement	Acknowledgment	False	Information only	False
Priority	0	Display class	0	Report	False
Created by	GRAPH	Date created	5/9/2026 9:57 PM	Last change	5/9/2026 9:57 PM
Group ID	0	Additional text 1		Additional text 2	
Additional text 3		Additional text 4		Additional text 5	
Additional text 6		Additional text 7		Additional text 8	
Additional text 9					
Name	 STEP_TIME_ALARM_INST	Type	PLC alarm	ID	55
Location	ProcessSequence_DB	Alarm text	@2%t#SYSTEM_Global_ProDiag_SupervisionCategories@ : @2%t#SYSTEM_Global_ProDiag_Supervision-Types@ : \$\$CpuName\$\$: ProcessSequence : @1%t#SYSTEM_Step-Names639139229409982114_1@ : S@1%03d@ : @1%t#SYSTEM_SupervisionAlarm-Texts639139229410057278_1@	Info text	
Alarm class	No Acknowledgement	Acknowledgment	False	Information only	False
Priority	0	Display class	0	Report	False
Created by	GRAPH	Date created	5/9/2026 9:57 PM	Last change	5/10/2026 1:33 PM
Group ID	0	Additional text 1		Additional text 2	
Additional text 3		Additional text 4		Additional text 5	
Additional text 6		Additional text 7		Additional text 8	
Additional text 9					
Name	 SUP_ALARM_INST	Type	PLC alarm	ID	
Location	ProcessSequence	Alarm text	Category : Supervision type : PLC name : FB name : Step name : Step number : Step specific field	Info text	
Alarm class	No Acknowledgement	Acknowledgment	False	Information only	False
Priority	0	Display class	0	Report	False
Created by	GRAPH	Date created	5/9/2026 9:57 PM	Last change	5/9/2026 9:57 PM
Group ID	0	Additional text 1		Additional text 2	
Additional text 3		Additional text 4		Additional text 5	
Additional text 6		Additional text 7		Additional text 8	
Additional text 9					
Name	 SUP_ALARM_INST	Type	PLC alarm	ID	54
Location	ProcessSequence_DB	Alarm text	@2%t#SYSTEM_Global_ProDiag_SupervisionCategories@ : @2%t#SYSTEM_Global_ProDiag_Supervision-Types@ : \$\$CpuName\$\$: ProcessSequence : @1%t#SYSTEM_Step-Names639139229409982114_1@ : S@1%03d@ : @1%t#SYSTEM_SupervisionAlarm-Texts639139229410057278_1@	Info text	
Alarm class	No Acknowledgement	Acknowledgment	False	Information only	False
Priority	0	Display class	0	Report	False
Created by	GRAPH	Date created	5/9/2026 9:57 PM	Last change	5/10/2026 1:33 PM
Group ID	0	Additional text 1		Additional text 2	

--	--	--

Totally Integrated Automation Portal		
Additional text 3 Additional text 6 Additional text 9		Additional text 4 Additional text 7
		Additional text 5 Additional text 8

Totally Integrated Automation Portal			
ChemicalProcess / PLC_1 [CPU 1511-1 PN] / PLC supervisions & alarms			
System alarms			
System alarms			
Name	 SDIAG_ALCAT_SUBMODUL_MSG_0002	Type	PLC alarm
ID	1	Location	PLC_1
Alarm text	Error: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_MODUL_MSG_0003	Type	PLC alarm
ID	2	Location	PLC_1
Alarm text	Error: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_RACK_MSG_0004	Type	PLC alarm
ID	3	Location	PLC_1
Alarm text	Error: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_DEVICE_MSG_0005	Type	PLC alarm
ID	4	Location	PLC_1
Alarm text	Error: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_IOSYSTEM_MSG_0006	Type	PLC alarm
ID	5	Location	PLC_1
Alarm text	Error: @1W%t#7W@ @5W%t#7W@ @6W%t#276K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_CPU_OST_MSG_000D	Type	PLC alarm
ID	6	Location	PLC_1
Alarm text	CPU status message: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	

Totally Integrated Automation Portal					
Additional text 8				Additional text 9	
Name	 SDIAG_ALCAT_CPU_INFO_MSG_000F	Type	PLC alarm		
ID	7	Location	PLC_1		
Alarm text	CPU info: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@		
Alarm class	No Acknowledgement	Acknowledgment	False		
Information only	True	Priority	0		
Report	False	Created by	System diagnostics		
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM		
Group ID	0	Additional text 1	PLC_1		
Additional text 2		Additional text 3			
Additional text 4		Additional text 5			
Additional text 6		Additional text 7			
Additional text 8		Additional text 9			
Name	 SDIAG_ALCAT_CPU_ERR_MSG_0010	Type	PLC alarm		
ID	8	Location	PLC_1		
Alarm text	CPU error: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@		
Alarm class	No Acknowledgement	Acknowledgment	False		
Information only	True	Priority	0		
Report	False	Created by	System diagnostics		
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM		
Group ID	0	Additional text 1	PLC_1		
Additional text 2		Additional text 3			
Additional text 4		Additional text 5			
Additional text 6		Additional text 7			
Additional text 8		Additional text 9			
Name	 SDIAG_ALCAT_CPU_MD_MSG_0011	Type	PLC alarm		
ID	9	Location	PLC_1		
Alarm text	CPU maintenance demanded: @1W%t#7W@ @6W%t#257K@ / @5W%t#7W@ @6W%t#258K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@		
Alarm class	No Acknowledgement	Acknowledgment	False		
Information only	True	Priority	0		
Report	False	Created by	System diagnostics		
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM		
Group ID	0	Additional text 1	PLC_1		
Additional text 2		Additional text 3			
Additional text 4		Additional text 5			
Additional text 6		Additional text 7			
Additional text 8		Additional text 9			
Name	 SDIAG_ALCAT_CPU_MR_MSG1_0012	Type	PLC alarm		
ID	10	Location	PLC_1		
Alarm text	CPU maintenance required: @1W%t#7W@ @6W%t#257K@ / @5W%t#7W@ @6W%t#258K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@		
Alarm class	No Acknowledgement	Acknowledgment	False		
Information only	True	Priority	0		
Report	False	Created by	System diagnostics		
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM		
Group ID	0	Additional text 1	PLC_1		
Additional text 2		Additional text 3			
Additional text 4		Additional text 5			
Additional text 6		Additional text 7			
Additional text 8		Additional text 9			
Name	 SDIAG_ALCAT_CPU_TMPERR_MSG_0013	Type	PLC alarm		
ID	11	Location	PLC_1		
Alarm text	Temporary CPU error: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@		
Alarm class	No Acknowledgement	Acknowledgment	False		
Information only	True	Priority	0		
Report	False	Created by	System diagnostics		
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM		
Group ID	0	Additional text 1	PLC_1		
Additional text 2		Additional text 3			
Additional text 4		Additional text 5			
Additional text 6		Additional text 7			
Additional text 8		Additional text 9			
Name	 SDIAG_ALCAT_CH_ERR_MSG_0015	Type	PLC alarm		
ID	12	Location	PLC_1		
Alarm text	Error: @1W%t#7W@ on @8W%t#280K@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@		
Alarm class	No Acknowledgement	Acknowledgment	False		
Information only	True	Priority	0		
Report	False	Created by	System diagnostics		
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM		
Group ID	0	Additional text 1	PLC_1		
Additional text 2		Additional text 3			
Additional text 4		Additional text 5			
Additional text 6		Additional text 7			
Additional text 8		Additional text 9			

--	--	--

Totally Integrated Automation Portal			
Name	 SDIAG_ALCAT_ECH_ERR_MSG_0016	Type	PLC alarm
ID	13	Location	PLC_1
Alarm text	Error: @1W%t#7W@ - @5W%t#7W@ on @8W%t#280K@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_CH_MD_MSG_0018	Type	PLC alarm
ID	14	Location	PLC_1
Alarm text	Maintenance demanded:@1W%t#7W@ on @8W%t#280K@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_ECH_MD_MSG_0019	Type	PLC alarm
ID	15	Location	PLC_1
Alarm text	Maintenance demanded:@1W%t#7W@ - @5W%t#7W@ on @8W%t#280K@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_CH_MR_MSG_001B	Type	PLC alarm
ID	16	Location	PLC_1
Alarm text	Maintenance required:@1W%t#7W@ on @8W%t#280K@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_ECH_MR_MSG_001C	Type	PLC alarm
ID	17	Location	PLC_1
Alarm text	Maintenance required:@1W%t#7W@ - @5W%t#7W@ on @8W%t#280K@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_SUB_ERR_MSG_001E	Type	PLC alarm
ID	18	Location	PLC_1
Alarm text	Error: @1W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	

Totally Integrated Automation Portal			
Name	 SDIAG_ALCAT_ESUB_ERR_MSG_001F	Type	PLC alarm
ID	19	Location	PLC_1
Alarm text	Error: @1W%t#7W@ - @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_SUB_MD_MSG_0021	Type	PLC alarm
ID	20	Location	PLC_1
Alarm text	Maintenance demanded: @1W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_ESUB_MD_MSG_0022	Type	PLC alarm
ID	21	Location	PLC_1
Alarm text	Maintenance demanded: @1W%t#7W@ - @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_SUB_MR_MSG_0024	Type	PLC alarm
ID	22	Location	PLC_1
Alarm text	Maintenance required: @1W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_ESUB_MR_MSG_0025	Type	PLC alarm
ID	23	Location	PLC_1
Alarm text	Maintenance required: @1W%t#7W@ - @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_CONFIG_INFO_0028	Type	PLC alarm
ID	24	Location	PLC_1
Alarm text	Info: @1W%t#7W@ - @5W%t#7W@ @6W%t#257K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_CONFIG_REPORT_0029	Type	PLC alarm
ID	25	Location	PLC_1

Totally Integrated Automation Portal			
Alarm text	Info: @1W%t#7W@ - @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_SECU_EV_MSG_005E	Type	PLC alarm
ID	26	Location	PLC_1
Alarm text	Security event: @1W%t#7W@ @5W%t#7W@ @6W%t#258K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	Security
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_SECU_EV_INFO_005F	Type	PLC alarm
ID	27	Location	PLC_1
Alarm text	Security information: @1W%t#7W@ @5W%t#7W@ @6W%t#258K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	Security
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_USER_MSG_0080	Type	PLC alarm
ID	28	Location	PLC_1
Alarm text	User message: @1W%t#2W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_PLC_MSG_00FF	Type	PLC alarm
ID	29	Location	PLC_1
Alarm text	PLC notification: @1W%t#7W@ @5W%t#7W@ @6W%t#256K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	True	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_SUBMODUL_MSG_0102	Type	PLC alarm
ID	30	Location	PLC_1
Alarm text	Error: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	False	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_MODUL_MSG_0103	Type	PLC alarm
ID	31	Location	PLC_1
Alarm text	Error: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	False	Priority	0

Totally Integrated Automation Portal			
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_RACK_MSG_0104	Type	PLC alarm
ID	32	Location	PLC_1
Alarm text	Error: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	False	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_DEVICE_MSG_0105	Type	PLC alarm
ID	33	Location	PLC_1
Alarm text	Error: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	False	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_IOSYSTEM_MSG_0106	Type	PLC alarm
ID	34	Location	PLC_1
Alarm text	Error: @1W%t#7W@ @5W%t#7W@ @6W%t#276K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	False	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_CPU_OST_MSG_010D	Type	PLC alarm
ID	35	Location	PLC_1
Alarm text	CPU status message: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	False	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_CPU_ERR_MSG_0110	Type	PLC alarm
ID	36	Location	PLC_1
Alarm text	CPU error: @1W%t#7W@ @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	False	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_CPU_MD_MSG_0111	Type	PLC alarm
ID	37	Location	PLC_1
Alarm text	CPU maintenance demanded: @1W%t#7W@ @6W%t#257K@ / @5W%t#7W@ @6W%t#258K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	False	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	

Totally Integrated Automation Portal					
Additional text 4				Additional text 5	
Additional text 6				Additional text 7	
Additional text 8				Additional text 9	
Name	 SDIAG_ALCAT_CPU_MR_MSG1_0112	Type	PLC alarm		
ID	38	Location	PLC_1		
Alarm text	CPU maintenance required: @1W%t#7W@ @6W%t#257K@ / @5W%t#7W@ @6W%t#258K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@		
Alarm class	No Acknowledgement	Acknowledgment	False		
Information only	False	Priority	0		
Report	False	Created by	System diagnostics		
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM		
Group ID	0	Additional text 1	PLC_1		
Additional text 2		Additional text 3			
Additional text 4		Additional text 5			
Additional text 6		Additional text 7			
Additional text 8		Additional text 9			
Name	 SDIAG_ALCAT_CH_ERR_MSG_0115	Type	PLC alarm		
ID	39	Location	PLC_1		
Alarm text	Error: @1W%t#7W@ on @8W%t#280K@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@		
Alarm class	No Acknowledgement	Acknowledgment	False		
Information only	False	Priority	0		
Report	False	Created by	System diagnostics		
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM		
Group ID	0	Additional text 1	PLC_1		
Additional text 2		Additional text 3			
Additional text 4		Additional text 5			
Additional text 6		Additional text 7			
Additional text 8		Additional text 9			
Name	 SDIAG_ALCAT_ECH_ERR_MSG_0116	Type	PLC alarm		
ID	40	Location	PLC_1		
Alarm text	Error: @1W%t#7W@ - @5W%t#7W@ on @8W%t#280K@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@		
Alarm class	No Acknowledgement	Acknowledgment	False		
Information only	False	Priority	0		
Report	False	Created by	System diagnostics		
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM		
Group ID	0	Additional text 1	PLC_1		
Additional text 2		Additional text 3			
Additional text 4		Additional text 5			
Additional text 6		Additional text 7			
Additional text 8		Additional text 9			
Name	 SDIAG_ALCAT_CH_MD_MSG_0118	Type	PLC alarm		
ID	41	Location	PLC_1		
Alarm text	Maintenance demanded:@1W%t#7W@ on @8W%t#280K@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@		
Alarm class	No Acknowledgement	Acknowledgment	False		
Information only	False	Priority	0		
Report	False	Created by	System diagnostics		
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM		
Group ID	0	Additional text 1	PLC_1		
Additional text 2		Additional text 3			
Additional text 4		Additional text 5			
Additional text 6		Additional text 7			
Additional text 8		Additional text 9			
Name	 SDIAG_ALCAT_ECH_MD_MSG_0119	Type	PLC alarm		
ID	42	Location	PLC_1		
Alarm text	Maintenance demanded:@1W%t#7W@ - @5W%t#7W@ on @8W%t#280K@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@		
Alarm class	No Acknowledgement	Acknowledgment	False		
Information only	False	Priority	0		
Report	False	Created by	System diagnostics		
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM		
Group ID	0	Additional text 1	PLC_1		
Additional text 2		Additional text 3			
Additional text 4		Additional text 5			
Additional text 6		Additional text 7			
Additional text 8		Additional text 9			
Name	 SDIAG_ALCAT_CH_MR_MSG_011B	Type	PLC alarm		
ID	43	Location	PLC_1		
Alarm text	Maintenance required:@1W%t#7W@ on @8W%t#280K@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@		
Alarm class	No Acknowledgement	Acknowledgment	False		
Information only	False	Priority	0		
Report	False	Created by	System diagnostics		
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM		
Group ID	0	Additional text 1	PLC_1		
Additional text 2		Additional text 3			
Additional text 4		Additional text 5			

Totally Integrated Automation Portal					
Additional text 6				Additional text 7	
Additional text 8				Additional text 9	
Name		 SDIAG_ALCAT_ECH_MR_MSG_011C		Type	
ID		44		Location	
Alarm text		Maintenance required:@1W%t#7W@ - @5W%t#7W@ on @8W%t#280K@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@		Info text	
Alarm class		No Acknowledgement		Acknowledgment	
Information only		False		Priority	
Report		False		Created by	
Date created		9/20/2021 12:56 PM		Last change	
Group ID		0		Additional text 1	
Additional text 2				Additional text 3	
Additional text 4				Additional text 5	
Additional text 6				Additional text 7	
Additional text 8				Additional text 9	
Name		 SDIAG_ALCAT_SUB_ERR_MSG_011E		Type	
ID		45		Location	
Alarm text		Error: @1W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@		Info text	
Alarm class		No Acknowledgement		Acknowledgment	
Information only		False		Priority	
Report		False		Created by	
Date created		9/20/2021 12:56 PM		Last change	
Group ID		0		Additional text 1	
Additional text 2				Additional text 3	
Additional text 4				Additional text 5	
Additional text 6				Additional text 7	
Additional text 8				Additional text 9	
Name		 SDIAG_ALCAT_ESUB_ERR_MSG_011F		Type	
ID		46		Location	
Alarm text		Error: @1W%t#7W@ - @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@		Info text	
Alarm class		No Acknowledgement		Acknowledgment	
Information only		False		Priority	
Report		False		Created by	
Date created		9/20/2021 12:56 PM		Last change	
Group ID		0		Additional text 1	
Additional text 2				Additional text 3	
Additional text 4				Additional text 5	
Additional text 6				Additional text 7	
Additional text 8				Additional text 9	
Name		 SDIAG_ALCAT_SUB_MD_MSG_0121		Type	
ID		47		Location	
Alarm text		Maintenance demanded: @1W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@		Info text	
Alarm class		No Acknowledgement		Acknowledgment	
Information only		False		Priority	
Report		False		Created by	
Date created		9/20/2021 12:56 PM		Last change	
Group ID		0		Additional text 1	
Additional text 2				Additional text 3	
Additional text 4				Additional text 5	
Additional text 6				Additional text 7	
Additional text 8				Additional text 9	
Name		 SDIAG_ALCAT_ESUB_MD_MSG_0122		Type	
ID		48		Location	
Alarm text		Maintenance demanded: @1W%t#7W@ - @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@		Info text	
Alarm class		No Acknowledgement		Acknowledgment	
Information only		False		Priority	
Report		False		Created by	
Date created		9/20/2021 12:56 PM		Last change	
Group ID		0		Additional text 1	
Additional text 2				Additional text 3	
Additional text 4				Additional text 5	
Additional text 6				Additional text 7	
Additional text 8				Additional text 9	
Name		 SDIAG_ALCAT_SUB_MR_MSG_0124		Type	
ID		49		Location	
Alarm text		Maintenance required: @1W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@		Info text	
Alarm class		No Acknowledgement		Acknowledgment	
Information only		False		Priority	
Report		False		Created by	
Date created		9/20/2021 12:56 PM		Last change	
Group ID		0		Additional text 1	
Additional text 2				Additional text 3	
Additional text 4				Additional text 5	
Additional text 6				Additional text 7	

--	--	--

Totally Integrated Automation Portal			
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_ESUB_MR_MSG_0125	Type	PLC alarm
ID	50	Location	PLC_1
Alarm text	Maintenance required: @1W%t#7W@ - @5W%t#7W@ @6W%t#257K@ / @6W%t#258K@.@6W%t#259K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	False	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_CONFIG_INFO_0128	Type	PLC alarm
ID	51	Location	PLC_1
Alarm text	Info: @1W%t#7W@ - @5W%t#7W@ @6W%t#257K@ @6W%t#262K@ @6W%t#263K@ @8W%t#7W@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	False	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	
Name	 SDIAG_ALCAT_PLC_MSG_01FF	Type	PLC alarm
ID	52	Location	PLC_1
Alarm text	PLC notification: @1W%t#7W@ @5W%t#7W@ @6W%t#256K@ @6W%t#262K@ @6W%t#263K@	Info text	Short name: @6W%t#260K@ Order number: @6W%t#265K@
Alarm class	No Acknowledgement	Acknowledgment	False
Information only	False	Priority	0
Report	False	Created by	System diagnostics
Date created	9/20/2021 12:56 PM	Last change	9/20/2021 12:56 PM
Group ID	0	Additional text 1	PLC_1
Additional text 2		Additional text 3	
Additional text 4		Additional text 5	
Additional text 6		Additional text 7	
Additional text 8		Additional text 9	

Totally Integrated Automation Portal		
--------------------------------------	--	--

ChemicalProcess / PLC_1 [CPU 1511-1 PN]

PLC alarm text lists

SYSTEM_StepNames639139229409982114_1

Selection	Decimal	ID	4095
Comment			

Text list entries of SYSTEM_StepNames639139229409982114_1

Range from	Range to	Entry
1	1	Start
2	2	Fill NaOH
3	3	Fill Powder M001
4	4	Start Mixing
5	5	Empty MIX Tank
6	6	Stop Water
7	7	Close NaOH valve
8	8	Powder Motor Stop
9	9	Stop Mixing
10	10	Empty Storage Tank
11	11	Stop emptying
12	12	Exit valve open
13	13	Step13
14	14	Not to Storage
15	15	Exit valve close
16	16	Valve 521 Stays open
17	17	Fill water
18	18	Step18

SYSTEM_SupervisionAlarmTexts639139229410057278_1

Selection	Decimal	ID	4094
Comment			

Text list entries of SYSTEM_SupervisionAlarmTexts639139229410057278_1

Range from	Range to	Entry
1	1	
2	2	
3	3	
4	4	
5	5	
6	6	
7	7	
8	8	
9	9	
10	10	
11	11	
12	12	
13	13	
14	14	
15	15	
16	16	
17	17	
18	18	

SYSTEM_InterlockAlarmTexts639139229410127278_1

Selection	Decimal	ID	4093
Comment			

Text list entries of SYSTEM_InterlockAlarmTexts639139229410127278_1

Range from	Range to	Entry
1	1	
2	2	
3	3	
4	4	
5	5	
6	6	
7	7	
8	8	
9	9	
10	10	
11	11	
12	12	
13	13	
14	14	
15	15	
16	16	
17	17	
18	18	

SYSTEM_TransitionNames639139229410197280_1

Selection	Decimal	ID	4092
Comment			

Text list entries of SYSTEM_TransitionNames639139229410197280_1

Range from	Range to	Entry
1	1	Trans1
2	2	Trans2

Totally Integrated Automation Portal		
Range from	Range to	Entry
3	3	Trans3
4	4	Trans4
5	5	Trans5
6	6	Trans6
7	7	Trans7
8	8	Trans8
9	9	Trans9
10	10	Trans10
11	11	Trans11
12	12	Trans12

Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Local modules

PS 25W 24VDC_1

PS 25W 24VDC_1

General\Project information

Name	PS 25W 24VDC_1	Author	amk1008619	Comment	
Rack number	0	Slot	0		

General\Catalog information

Short designation	PS 25W 24VDC	Description	System power supply 25W, 24VDC; supplies the operating voltage for the S7-1500 backplane bus.	Article number	6ES7 505-0KA00-0AB0
Firmware version	V1.0				

General\Identification & Maintenance

Plant designation		Location identifier		Installation date	2026-05-07 12:49:41.414
Additional information					

Module parameters\General\Startup

Comparison preset to actual module	From CPU				
------------------------------------	----------	--	--	--	--

PS 25W 24VDC\General

Name	PS 25W 24VDC_1	Comment			
------	----------------	---------	--	--	--

PS 25W 24VDC\Diagnostics

Supply voltage monitoring	False	Switch position off	False		
---------------------------	-------	---------------------	-------	--	--

Totally Integrated Automation Portal

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Local modules

PLC_1 [CPU 1511-1 PN]

PLC_1

General\Project information

Name	PLC_1	Author	mika3	Comment	
Rack	0	Slot	1		

General\Catalog information

Short designation	CPU 1511-1 PN	Description	CPU with display; work memory 150 KB code and 1 MB data; 60 ns bit operation time; 4-stage protection concept, technology functions: motion control, closed-loop control, counting and measuring; tracing; Runtime options; isochronous mode (central); for all PROFINET interfaces: transport protocol TCP/IP, secure Open User Communication, S7 communication, S7 routing, IP forwarding, Web server, DNS client, OPC UA: Server DA, Client DA, methods, companion specifications; PROFINET IO controller, supports RT/IRT, performance upgrade PROFINET V2.3, 2 ports, I-Device, MRP, MRPD, isochronous mode; firmware V2.8		
Article number	6ES7 511-1AK01-0AB0				
Firmware version	V2.8				

General\Identification & Maintenance

Plant designation		Location identifier		Installation date	2021-05-25 07:35:19.863
Additional information					

General\Checksums

Text lists	CB 3F BA AA D7 54 DC 4F	Software	Not available (compile necessary)		
------------	-------------------------	----------	-----------------------------------	--	--

PROFINET interface [X1]\General

Name	PROFINET interface_1	Author	mika3	Comment	
------	----------------------	--------	-------	---------	--

PROFINET interface [X1]\Ethernet addresses\Interface networked with

Subnet:	PN/IE_1				
---------	---------	--	--	--	--

PROFINET interface [X1]\Ethernet addresses\IP protocol

IP configuration	Set IP address in the project	IP address:	192.168.0.1	Subnet mask:	255.255.255.0
Use router	False				

PROFINET interface [X1]\Ethernet addresses\PROFINET

PROFINET device name is set directly at the device	False	Generate PROFINET device name automatically	True	PROFINET device name:	plc_1.profinet interface_1
Converted name:	plcxb1.profinetxainterfacexb1036c	Device number:	0		

PROFINET interface [X1]\Time-of-day synchronization\NTP mode

Note	Time synchronization for all PROFINET interfaces take place within the settings for time synchronization of the PROFINET interface [X1].	Enable time synchronization via NTP server	False		IP addresses
Server 1	0.0.0.0	Server 2	0.0.0.0	Server 3	0.0.0.0
Server 4	0.0.0.0	Update interval	10s		

PROFINET interface [X1]\Operating mode

IO controller	True	IO system		Device number	0
IO device	False				

PROFINET interface [X1]\Advanced options\Interface options

Call the user program if communication errors occur	False	Support device replacement without exchangeable medium	True	Permit overwriting of device names of all assigned IO devices	False
Limit data infeed into the network	True	Use IEC V2.2 LLDP mode	False	Keep-Alive connection monitoring:	30s

PROFINET interface [X1]\Advanced options\Media redundancy

MRP domain	mrpdomain-1	Media redundancy role:	Not device in the ring		
------------	-------------	------------------------	------------------------	--	--

PROFINET interface [X1]\Advanced options\Real time settings\IO communication

Send clock:	1.000ms				
-------------	---------	--	--	--	--

PROFINET interface [X1]\Advanced options\Real time settings\Synchronization

Sync domain:	Sync-Domain_1	Synchronization role:	Unsynchronized	RT class:	RT,IRT
--------------	---------------	-----------------------	----------------	-----------	--------

PROFINET interface [X1]\Advanced options\Real time settings\Real time options

Calculated bandwidth for cyclic IO data:	0.000ms	Calculated bandwidth for cyclic IO data:	0.000%		
--	---------	--	--------	--	--


PROFINET interface [X1]\Advanced options\Port [X1 P1 R]\General

Name	Port_1	Author	mika3	Comment	
------	--------	--------	-------	---------	--

PROFINET interface [X1]\Advanced options\Port [X1 P1 R]\Port interconnection\Local port:

Local port:	PLC_1\PROFINET interface_1 [X1]\Port_1 [X1 P1 R]	Medium:	Copper	Cable name:	---
-------------	--	---------	--------	-------------	-----



Totally Integrated Automation Portal						
PROFINET interface [X1]\Advanced options\Port [X1 P1 R]\Port interconnection\Partner port:						
	Monitoring of partner port is not possible	Alternative partners	False	Partner port:	Any partner	
PROFINET interface [X1]\Advanced options\Port [X1 P1 R]\Port options\Activate						
Activate this port for use	True					
PROFINET interface [X1]\Advanced options\Port [X1 P1 R]\Port options\Connection						
Transmission rate / duplex:	Automatic	Monitor	False	Enable autonegotiation	True	
PROFINET interface [X1]\Advanced options\Port [X1 P1 R]\Port options\Boundaries						
End of detection of accessible devices	False	End of topology discovery	False	End of the sync domain	False	
PROFINET interface [X1]\Advanced options\Port [X1 P2 R]\General						
Name	Port_2	Author	mika3	Comment		
PROFINET interface [X1]\Advanced options\Port [X1 P2 R]\Port interconnection\Local port:						
Local port:	PLC_1\PROFINET interface_1 [X1]\Port_2 [X1 P2 R]		Medium:	Copper	Cable name:	---
						
PROFINET interface [X1]\Advanced options\Port [X1 P2 R]\Port interconnection\Partner port:						
	Monitoring of partner port is not possible	Alternative partners	False	Partner port:	Any partner	
PROFINET interface [X1]\Advanced options\Port [X1 P2 R]\Port options\Activate						
Activate this port for use	True					
PROFINET interface [X1]\Advanced options\Port [X1 P2 R]\Port options\Connection						
Transmission rate / duplex:	Automatic	Monitor	False	Enable autonegotiation	True	
PROFINET interface [X1]\Advanced options\Port [X1 P2 R]\Port options\Boundaries						
End of detection of accessible devices	False	End of topology discovery	False	End of the sync domain	False	
PROFINET interface [X1]\Web server access						
Note	The Web server must also be activated in the properties of the PLC.		Enable Web server via IP address of this interface	False		
Startup						
Startup after POWER ON	Warm restart - Operating mode before POWER OFF	Comparison preset to actual configuration	Startup CPU even if mismatch	Configuration time	60000ms	
Cycle						
Maximum cycle time	150ms			Enable minimum cycle time for cyclic OBs	True	
Minimum cycle time	1ms					
Communication load						
Cycle load due to communication	50%					
System and clock memory\System memory bits						
Enable the use of system memory byte	False	Address of system memory byte (MBx)	1	First cycle		
Diagnostic status changed		Always 1 (high)		Always 0 (low)		
System and clock memory\Clock memory bits						
Enable the use of clock memory byte	False	Address of clock memory byte (MBx)	0	10 Hz clock		
5 Hz clock		2.5 Hz clock		2 Hz clock		
1.25 Hz clock		1 Hz clock		0.625 Hz clock		
0.5 Hz clock						
SIMATIC Memory Card\Diagnostics						
Aging of the SIMATIC memory card	False	Threshold value	80%			
System diagnostics\General						
Activate system diagnostics for this device	True	Report network faults as maintenance instead of fault	False			
PLC alarms\General						
Central alarm management in the PLC	True					
Web server\General						
Activate web server on this module	False	Permit access only with HTTPS	True			
Web server\Automatic update						
Enable automatic update	True	Update interval	0s			
Web server\User management						
User name			User rights			
Everybody						
Web server\User-defined web pages						
Application name	HTML source path	Default HTML page	Files with dynamic content	Web DB number	Fragment DB number	
		index.htm	.htm;.html	333	334	
Web server\Overview of interfaces						
Device		Interface		Enabled web server access		
PLC_1		PROFINET interface_1		False		

Totally Integrated Automation Portal		
--------------------------------------	--	--

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Local modules

DI 16x24VDC BA_1

DI 16x24VDC BA_1

General\Project information

Name	DI 16x24VDC BA_1	Author	mika3	Comment	
Rack	0	Slot	2		

General\Catalog information

Short designation	DI 16x24VDC BA	Description	Digital input module DI16 x 24VDC; grouping 16; input delay 3.2ms; input type 3 (IEC 61131)	Article number	6ES7 521-1BH10-0AA0
Firmware version	V1.1				

General\Identification & Maintenance

Plant designation		Location identifier		Installation date	2021-05-25 07:46:32.651
Additional information					

Module parameters\General\Startup

Comparison preset to actual module	From CPU	
------------------------------------	----------	--

Module parameters\DI Configuration\Configuration of submodules

Module distribution	None	
---------------------	------	--

Module parameters\DI Configuration\Value status (Quality Information)

Value status	False	
--------------	-------	--

Module parameters\DI Configuration\Copy of module for Shared Device (MSI)

Copy of module:	None	
-----------------	------	--

Input 0 - 15\General

Name	DI 16x24VDC BA_1	Comment	
------	------------------	---------	--

Input 0 - 15\Inputs\General\Module failure

Input values with module failure	Input value 0	
----------------------------------	---------------	--

Input 0 - 15\I/O addresses\Input addresses

Start address	0.0	End address	1.7	Organization block	0
Process image	0				

Totally Integrated Automation Portal		
--------------------------------------	--	--

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Local modules

DQ 16x24VDC/0.5A BA_1

DQ 16x24VDC/0.5A BA_1

General\Project information

Name	DQ 16x24VDC/0.5A BA_1	Author	mika3	Comment	
Rack	0	Slot	3		

General\Catalog information

Short designation	DQ 16x24VDC/0.5A BA	Description	Digital output module DQ16 x 24VDC / 0.5A; grouping 8; 4A per group	Article number	6ES7 522-1BH10-0AA0
Firmware version	V1.1				

General\Identification & Maintenance

Plant designation		Location identifier		Installation date	2021-05-25 07:46:40.812
Additional information					

Module parameters\General\Startup

Comparison preset to actual module	From CPU	
------------------------------------	----------	--

Module parameters\DQ configuration\Configuration of submodules

Module distribution	None	
---------------------	------	--

Module parameters\DQ configuration\Value status (Quality Information)

Value status	False	
--------------	-------	--

Module parameters\DQ configuration\Copy of module for shared device (MSO)

Copy of module:	None	
-----------------	------	--

Output 0 - 15\General

Name	DQ 16x24VDC/0.5A BA_1	Comment		
------	-----------------------	---------	--	--

Output 0 - 15\I/O addresses\Output addresses

Start address	0.0	End address	1.7	Organization block	0
Process image	0				

Totally Integrated Automation Portal		
--------------------------------------	--	--

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Local modules

AI 8xU//RTD/TC ST_1

AI 8xU//RTD/TC ST_1

General\Project information

Name	AI 8xU//RTD/TC ST_1	Author	mika3	Comment	
Rack	0	Slot	4		

General\Catalog information

Short designation	AI 8xU//RTD/TC ST	Description	Analog input module AI8 x U//RTD/TC 16-bit; grouping 8; 4 channels with RTD measurement; common mode voltage 10 V; configurable diagnostics; hardware interrupts	Article number	6ES7 531-7KF00-0AB0
Firmware version	V2.2				

General\Identification & Maintenance

Plant designation		Location identifier		Installation date	2021-05-25 07:47:04.964
Additional information					

Module parameters\General\Startup

Comparison preset to actual module	From CPU		
------------------------------------	----------	--	--

Module parameters\Channel template\Inputs\Apply to all channels that use the template\Diagnostics

No supply voltage L+	False	Overflow	False	Underflow	False
Common mode error	False	Reference junction	False	Wire break	False
Current limit for wire break diagnostics					

Module parameters\Channel template\Inputs\Apply to all channels that use the template\Measuring

Measurement type	Current (2-wire transducer)	Measuring range	4..20mA	Temperature coefficient	
Temperature unit		Reference junction		Fixed reference temperature	
Interference frequency suppression	50Hz	Smoothing	None		

Module parameters\AI configuration\Configuration of submodules

Module distribution	None		
---------------------	------	--	--

Module parameters\AI configuration\Value status (Quality Information)

Value status	False		
--------------	-------	--	--

Module parameters\AI configuration\Copy of module for Shared Device (MSI)

Copy of module:	None		
-----------------	------	--	--

Input 0 - 7\General

Name	AI 8xU//RTD/TC ST_1	Comment		
------	---------------------	---------	--	--

Input 0 - 7\Inputs\Channel 0

Parameter settings	From template		
--------------------	---------------	--	--

Input 0 - 7\Inputs\Channel 0\Diagnostics

No supply voltage L+	False	Overflow	False	Underflow	False
Common mode error	False	Reference junction	False	Wire break	False
Current limit for wire break diagnostics					

Input 0 - 7\Inputs\Channel 0\Measuring

Measurement type	Current (2-wire transducer)	Measuring range	4..20mA	Temperature coefficient	
Temperature unit		Reference junction		Fixed reference temperature	
Interference frequency suppression	50Hz	Smoothing	None		

Input 0 - 7\Inputs\Channel 0\Hardware interrupts

High limit 1		Low limit 1		High limit 2	
Low limit 2					

Input 0 - 7\Inputs\Channel 0\Hardware interrupts\

Hardware interrupt high limit 1	0	RidPrefixFallingEdgeEvent	49272	Event name:	
Hardware interrupt:	0	UpperLimitOne0	UpperLimitOne0	Channel number	0
HwEventTypeLimit1Overrun	4				

Input 0 - 7\Inputs\Channel 0\Hardware interrupts\

Hardware interrupt low limit 1	0	RidPrefixFallingEdgeEvent	49288	Event name:	
Hardware interrupt:	0	LowerLimitOne0	LowerLimitOne0	Channel number	0
HwEventTypeLimit1Underrun	3				

Input 0 - 7\Inputs\Channel 0\Hardware interrupts\

Hardware interrupt high limit 2	0	RidPrefixFallingEdgeEvent	49264	Event name:	
Hardware interrupt:	0	UpperLimitTwo0	UpperLimitTwo0	Channel number	0
HwEventTypeLimit2Overrun	6				

Input 0 - 7\Inputs\Channel 0\Hardware interrupts\

Hardware interrupt low limit 2	0	RidPrefixFallingEdgeEvent	49280	Event name:	
Hardware interrupt:	0	LowerLimitTwo0	LowerLimitTwo0	Channel number	0
HwEventTypeLimit2Underrun	5				

Input 0 - 7\Inputs\Channel 1

Parameter settings	From template		
--------------------	---------------	--	--

Input 0 - 7\Inputs\Channel 1\Diagnostics

No supply voltage L+	False	Overflow	False	Underflow	False
----------------------	-------	----------	-------	-----------	-------

Totally Integrated Automation Portal							
Common mode error		False	Reference junction	False	Wire break	False	
Current limit for wire break diagnostics							
Input 0 - 7\Inputs\Channel 1\Measuring							
Measurement type	Current (2-wire transducer)	Measuring range	4..20mA	Temperature coefficient			
Temperature unit		Reference junction		Fixed reference temperature			
Interference frequency suppression	50Hz	Smoothing	None				
Input 0 - 7\Inputs\Channel 1\Hardware interrupts							
High limit 1		Low limit 1		High limit 2			
Low limit 2							
Input 0 - 7\Inputs\Channel 1\Hardware interrupts\							
Hardware interrupt high limit 1	0	RidPrefixFallingEdgeEvent	49273	Event name:			
Hardware interrupt:	0	UpperLimitOne1	UpperLimitOne1	Channel number	1		
HwEventTypeLimit1Overrun	4						
Input 0 - 7\Inputs\Channel 1\Hardware interrupts\							
Hardware interrupt low limit 1	0	RidPrefixFallingEdgeEvent	49289	Event name:			
Hardware interrupt:	0	LowerLimitOne1	LowerLimitOne1	Channel number	1		
HwEventTypeLimit1Underrun	3						
Input 0 - 7\Inputs\Channel 1\Hardware interrupts\							
Hardware interrupt high limit 2	0	RidPrefixFallingEdgeEvent	49265	Event name:			
Hardware interrupt:	0	UpperLimitTwo1	UpperLimitTwo1	Channel number	1		
HwEventTypeLimit2Overrun	6						
Input 0 - 7\Inputs\Channel 1\Hardware interrupts\							
Hardware interrupt low limit 2	0	RidPrefixFallingEdgeEvent	49281	Event name:			
Hardware interrupt:	0	LowerLimitTwo1	LowerLimitTwo1	Channel number	1		
HwEventTypeLimit2Underrun	5						
Input 0 - 7\Inputs\Channel 2							
Parameter settings	From template						
Input 0 - 7\Inputs\Channel 2\Diagnostics							
No supply voltage L+	False	Overflow	False	Underflow	False		
Common mode error	False	Reference junction	False	Wire break	False		
Current limit for wire break diagnostics							
Input 0 - 7\Inputs\Channel 2\Measuring							
Measurement type	Current (2-wire transducer)	Measuring range	4..20mA	Temperature coefficient			
Temperature unit		Reference junction		Fixed reference temperature			
Interference frequency suppression	50Hz	Smoothing	None				
Input 0 - 7\Inputs\Channel 2\Hardware interrupts							
High limit 1		Low limit 1		High limit 2			
Low limit 2							
Input 0 - 7\Inputs\Channel 2\Hardware interrupts\							
Hardware interrupt high limit 1	0	RidPrefixFallingEdgeEvent	49274	Event name:			
Hardware interrupt:	0	UpperLimitOne2	UpperLimitOne2	Channel number	2		
HwEventTypeLimit1Overrun	4						
Input 0 - 7\Inputs\Channel 2\Hardware interrupts\							
Hardware interrupt low limit 1	0	RidPrefixFallingEdgeEvent	49290	Event name:			
Hardware interrupt:	0	LowerLimitOne2	LowerLimitOne2	Channel number	2		
HwEventTypeLimit1Underrun	3						
Input 0 - 7\Inputs\Channel 2\Hardware interrupts\							
Hardware interrupt high limit 2	0	RidPrefixFallingEdgeEvent	49266	Event name:			
Hardware interrupt:	0	UpperLimitTwo2	UpperLimitTwo2	Channel number	2		
HwEventTypeLimit2Overrun	6						
Input 0 - 7\Inputs\Channel 2\Hardware interrupts\							
Hardware interrupt low limit 2	0	RidPrefixFallingEdgeEvent	49282	Event name:			
Hardware interrupt:	0	LowerLimitTwo2	LowerLimitTwo2	Channel number	2		
HwEventTypeLimit2Underrun	5						
Input 0 - 7\Inputs\Channel 3							
Parameter settings	From template						
Input 0 - 7\Inputs\Channel 3\Diagnostics							
No supply voltage L+	False	Overflow	False	Underflow	False		
Common mode error	False	Reference junction	False	Wire break	False		
Current limit for wire break diagnostics							
Input 0 - 7\Inputs\Channel 3\Measuring							
Measurement type	Current (2-wire transducer)	Measuring range	4..20mA	Temperature coefficient			

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Temperature unit		Reference junction		Fixed reference temperature	
Interference frequency suppression	50Hz	Smoothing	None		
Input 0 - 7\Inputs\Channel 3\Hardware interrupts					
High limit 1		Low limit 1		High limit 2	
Low limit 2					
Input 0 - 7\Inputs\Channel 3\Hardware interrupts\					
Hardware interrupt high limit 1	0	RidPrefixFallingEdgeEvent	49275	Event name:	
Hardware interrupt:	0	UpperLimitOne3	UpperLimitOne3	Channel number	3
HwEventTypeLimit1Overrun	4				
Input 0 - 7\Inputs\Channel 3\Hardware interrupts\					
Hardware interrupt low limit 1	0	RidPrefixFallingEdgeEvent	49291	Event name:	
Hardware interrupt:	0	LowerLimitOne3	LowerLimitOne3	Channel number	3
HwEventTypeLimit1Underrun	3				
Input 0 - 7\Inputs\Channel 3\Hardware interrupts\					
Hardware interrupt high limit 2	0	RidPrefixFallingEdgeEvent	49267	Event name:	
Hardware interrupt:	0	UpperLimitTwo3	UpperLimitTwo3	Channel number	3
HwEventTypeLimit2Overrun	6				
Input 0 - 7\Inputs\Channel 3\Hardware interrupts\					
Hardware interrupt low limit 2	0	RidPrefixFallingEdgeEvent	49283	Event name:	
Hardware interrupt:	0	LowerLimitTwo3	LowerLimitTwo3	Channel number	3
HwEventTypeLimit2Underrun	5				
Input 0 - 7\Inputs\Channel 4					
Parameter settings	From template				
Input 0 - 7\Inputs\Channel 4\Diagnostics					
No supply voltage L+	False	Overflow	False	Underflow	False
Common mode error	False	Reference junction	False	Wire break	False
Current limit for wire break diagnostics					
Input 0 - 7\Inputs\Channel 4\Measuring					
Measurement type	Current (2-wire transducer)	Measuring range	4..20mA	Temperature coefficient	
Temperature unit		Reference junction		Fixed reference temperature	
Interference frequency suppression	50Hz	Smoothing	None		
Input 0 - 7\Inputs\Channel 4\Hardware interrupts					
High limit 1		Low limit 1		High limit 2	
Low limit 2					
Input 0 - 7\Inputs\Channel 4\Hardware interrupts\					
Hardware interrupt high limit 1	0	RidPrefixFallingEdgeEvent	49276	Event name:	
Hardware interrupt:	0	UpperLimitOne4	UpperLimitOne4	Channel number	4
HwEventTypeLimit1Overrun	4				
Input 0 - 7\Inputs\Channel 4\Hardware interrupts\					
Hardware interrupt low limit 1	0	RidPrefixFallingEdgeEvent	49292	Event name:	
Hardware interrupt:	0	LowerLimitOne4	LowerLimitOne4	Channel number	4
HwEventTypeLimit1Underrun	3				
Input 0 - 7\Inputs\Channel 4\Hardware interrupts\					
Hardware interrupt high limit 2	0	RidPrefixFallingEdgeEvent	49268	Event name:	
Hardware interrupt:	0	UpperLimitTwo4	UpperLimitTwo4	Channel number	4
HwEventTypeLimit2Overrun	6				
Input 0 - 7\Inputs\Channel 4\Hardware interrupts\					
Hardware interrupt low limit 2	0	RidPrefixFallingEdgeEvent	49284	Event name:	
Hardware interrupt:	0	LowerLimitTwo4	LowerLimitTwo4	Channel number	4
HwEventTypeLimit2Underrun	5				
Input 0 - 7\Inputs\Channel 5					
Parameter settings	Manual				
Input 0 - 7\Inputs\Channel 5\Diagnostics					
No supply voltage L+	False	Overflow	False	Underflow	False
Common mode error	False	Reference junction	False	Wire break	False
Current limit for wire break diagnostics					
Input 0 - 7\Inputs\Channel 5\Measuring					
Measurement type	Deactivated	Measuring range		Temperature coefficient	
Temperature unit		Reference junction		Fixed reference temperature	
Interference frequency suppression		Smoothing			
Input 0 - 7\Inputs\Channel 5\Hardware interrupts					
High limit 1		Low limit 1		High limit 2	
Low limit 2					

--	--	--

Totally Integrated Automation Portal						
Input 0 - 7\Inputs\Channel 5\Hardware interrupts\						
Hardware interrupt high limit 1	0	RidPrefixFallingEdgeEvent	49277	Event name:		
Hardware interrupt:	0	UpperLimitOne5	UpperLimitOne5	Channel number	5	
HwEventTypeLimit1Overrun	4					
Input 0 - 7\Inputs\Channel 5\Hardware interrupts\						
Hardware interrupt low limit 1	0	RidPrefixFallingEdgeEvent	49293	Event name:		
Hardware interrupt:	0	LowerLimitOne5	LowerLimitOne5	Channel number	5	
HwEventTypeLimit1Underrun	3					
Input 0 - 7\Inputs\Channel 5\Hardware interrupts\						
Hardware interrupt high limit 2	0	RidPrefixFallingEdgeEvent	49269	Event name:		
Hardware interrupt:	0	UpperLimitTwo5	UpperLimitTwo5	Channel number	5	
HwEventTypeLimit2Overrun	6					
Input 0 - 7\Inputs\Channel 5\Hardware interrupts\						
Hardware interrupt low limit 2	0	RidPrefixFallingEdgeEvent	49285	Event name:		
Hardware interrupt:	0	LowerLimitTwo5	LowerLimitTwo5	Channel number	5	
HwEventTypeLimit2Underrun	5					
Input 0 - 7\Inputs\Channel 6						
Parameter settings	Manual					
Input 0 - 7\Inputs\Channel 6\Diagnostics						
No supply voltage L+	False	Overflow	False	Underflow	False	
Common mode error	False	Reference junction	False	Wire break	False	
Current limit for wire break diagnostics						
Input 0 - 7\Inputs\Channel 6\Measuring						
Measurement type	Deactivated	Measuring range		Temperature coefficient		
Temperature unit		Reference junction		Fixed reference temperature		
Interference frequency suppression		Smoothing				
Input 0 - 7\Inputs\Channel 6\Hardware interrupts						
High limit 1		Low limit 1		High limit 2		
Low limit 2						
Input 0 - 7\Inputs\Channel 6\Hardware interrupts\						
Hardware interrupt high limit 1	0	RidPrefixFallingEdgeEvent	49278	Event name:		
Hardware interrupt:	0	UpperLimitOne6	UpperLimitOne6	Channel number	6	
HwEventTypeLimit1Overrun	4					
Input 0 - 7\Inputs\Channel 6\Hardware interrupts\						
Hardware interrupt low limit 1	0	RidPrefixFallingEdgeEvent	49294	Event name:		
Hardware interrupt:	0	LowerLimitOne6	LowerLimitOne6	Channel number	6	
HwEventTypeLimit1Underrun	3					
Input 0 - 7\Inputs\Channel 6\Hardware interrupts\						
Hardware interrupt high limit 2	0	RidPrefixFallingEdgeEvent	49270	Event name:		
Hardware interrupt:	0	UpperLimitTwo6	UpperLimitTwo6	Channel number	6	
HwEventTypeLimit2Overrun	6					
Input 0 - 7\Inputs\Channel 6\Hardware interrupts\						
Hardware interrupt low limit 2	0	RidPrefixFallingEdgeEvent	49286	Event name:		
Hardware interrupt:	0	LowerLimitTwo6	LowerLimitTwo6	Channel number	6	
HwEventTypeLimit2Underrun	5					
Input 0 - 7\Inputs\Channel 7						
Parameter settings	Manual					
Input 0 - 7\Inputs\Channel 7\Diagnostics						
No supply voltage L+	False	Overflow	False	Underflow	False	
Common mode error	False	Reference junction	False	Wire break	False	
Current limit for wire break diagnostics						
Input 0 - 7\Inputs\Channel 7\Measuring						
Measurement type	Deactivated	Measuring range		Temperature coefficient		
Temperature unit		Reference junction		Fixed reference temperature		
Interference frequency suppression		Smoothing				
Input 0 - 7\Inputs\Channel 7\Hardware interrupts						
High limit 1		Low limit 1		High limit 2		
Low limit 2						
Input 0 - 7\Inputs\Channel 7\Hardware interrupts\						
Hardware interrupt high limit 1	0	RidPrefixFallingEdgeEvent	49279	Event name:		
Hardware interrupt:	0	UpperLimitOne7	UpperLimitOne7	Channel number	7	
HwEventTypeLimit1Overrun	4					

Totally Integrated Automation Portal						
Input 0 - 7\Inputs\Channel 7\Hardware interrupts\						
Hardware interrupt low limit 1	0	RidPrefixFallingEdgeEvent	49295	Event name:		
Hardware interrupt:	0	LowerLimitOne7	LowerLimitOne7	Channel number	7	
HwEventTypeLimit1Underrun	3					
Input 0 - 7\Inputs\Channel 7\Hardware interrupts\						
Hardware interrupt high limit 2	0	RidPrefixFallingEdgeEvent	49271	Event name:		
Hardware interrupt:	0	UpperLimitTwo7	UpperLimitTwo7	Channel number	7	
HwEventTypeLimit2Overrun	6					
Input 0 - 7\Inputs\Channel 7\Hardware interrupts\						
Hardware interrupt low limit 2	0	RidPrefixFallingEdgeEvent	49287	Event name:		
Hardware interrupt:	0	LowerLimitTwo7	LowerLimitTwo7	Channel number	7	
HwEventTypeLimit2Underrun	5					
Input 0 - 7\Inputs\Channel reference temperature\Diagnostics						
No supply voltage L+	False	Overflow	False	Underflow	False	
Wire break	False					
Input 0 - 7\Inputs\Channel reference temperature\Measure						
Measurement type	Deactivated	Measuring range		Temperature coefficient		
Interference frequency suppression		Smoothing				
Input 0 - 7\I/O addresses\Input addresses						
Start address	2	End address	17	Organization block	0	
Process image	0					

AQ 2xU/I ST_1

AQ 2xU/I ST_1					
General\Project information					
Name	AQ 2xU/I ST_1	Author	mika3	Comment	
Rack	0	Slot	5		
General\Catalog information					
Short designation	AQ 2xU/I ST	Description	Analog output module AQ2 x U/I 16-bit; grouping 2; configurable diagnostics; substitute value for output	Article number	6ES7 532-5NB00-0AB0
Firmware version	V1.0				
General\Identification & Maintenance					
Plant designation		Location identifier		Installation date	2021-05-25 07:47:12.326
Additional information					
Module parameters\General\Startup					
Comparison preset to actual module	From CPU				
Module parameters\Channel template\Outputs\Apply to all channels that use the template\Diagnostics					
No supply voltage L+	False	Wire break	False	Short circuit to ground	False
Overflow	False	Underflow	False		
Module parameters\Channel template\Outputs\Apply to all channels that use the template\Output parameters					
Output type	Voltage	Output range	+/- 10V	Reaction to CPU STOP	Shutdown
Substitute value					
Module parameters\AQ configuration\Configuration of submodules					
Module distribution	None				
Module parameters\AQ configuration\Value status (Quality Information)					
Value status	False				
Module parameters\AQ configuration\Copy of module for shared device (MSO)					
Copy of module:	None				
Output 0 - 1\General					
Name	AQ 2xU/I ST_1	Comment			
Output 0 - 1\Outputs\Channel 0					
Parameter settings	From template				
Output 0 - 1\Outputs\Channel 0\Diagnostics					
No supply voltage L+	False	Wire break	False	Short circuit to ground	False
Overflow	False	Underflow	False		
Output 0 - 1\Outputs\Channel 0\Output					
Output type	Voltage	Output range	+/- 10V	Reaction to CPU STOP	Shutdown
Substitute value					
Output 0 - 1\Outputs\Channel 1					
Parameter settings	From template				
Output 0 - 1\Outputs\Channel 1\Diagnostics					
No supply voltage L+	False	Wire break	False	Short circuit to ground	False
Overflow	False	Underflow	False		
Output 0 - 1\Outputs\Channel 1\Output					
Output type	Voltage	Output range	+/- 10V	Reaction to CPU STOP	Shutdown
Substitute value					
Output 0 - 1\I/O addresses\Output addresses					
Start address	2	End address	5	Organization block	0
Process image	0				

Totally Integrated Automation Portal		
--------------------------------------	--	--

ChemicalProcess / PLC_1 [CPU 1511-1 PN] / Local modules

DI 16x24VDC BA_2

DI 16x24VDC BA_2

General\Project information

Name	DI 16x24VDC BA_2	Author	mika3	Comment	
Rack	0	Slot	6		

General\Catalog information

Short designation	DI 16x24VDC BA	Description	Digital input module DI16 x 24VDC; grouping 16; input delay 3.2ms; input type 3 (IEC 61131)	Article number	6ES7 521-1BH10-0AA0
Firmware version	V1.1				

General\Identification & Maintenance

Plant designation		Location identifier		Installation date	2023-04-12 08:14:32.244
Additional information					

Module parameters\General\Startup

Comparison preset to actual module	From CPU	
------------------------------------	----------	--

Module parameters\DI Configuration\Configuration of submodules

Module distribution	None	
---------------------	------	--

Module parameters\DI Configuration\Value status (Quality Information)

Value status	False	
--------------	-------	--

Module parameters\DI Configuration\Copy of module for Shared Device (MSI)

Copy of module:	None	
-----------------	------	--

Input 0 - 15\General

Name	DI 16x24VDC BA_2	Comment	
------	------------------	---------	--

Input 0 - 15\Inputs\General\Module failure

Input values with module failure	Input value 0	
----------------------------------	---------------	--

Input 0 - 15\I/O addresses\Input addresses

Start address	18.0	End address	19.7	Organization block	0
Process image	0				

Totally Integrated Automation Portal				
ChemicalProcess HMI_1 [KTP700 Basic PN] HMI_1 General <table><tr><td>Name</td><td>HMI_1</td></tr></table>			Name	HMI_1
Name	HMI_1			

Totally Integrated Automation Portal

ChemicalProcess / HMI_1 [KTP700 Basic PN]

Runtime settings

General

Start screen	Root screen	Default template		Default style of the project	Enabled
Style of the HMI device	WinCC Dark V 1.0.1	Adapt font size to style	Enabled	Screen resolution	800, 480
Project ID	0	Logging language	Startup language		

Services

Sm@rtAccess or service: start Sm@rtServer	Disabled
---	----------

Screens

Bit selection for text and graphic lists	Off	User-defined pictogram size	Disabled	X,Y:	72, 51
Scrolling mode	Scroll bar				

Keyboard

Use screen keyboard	Enabled	Release button on exit	Disabled	Disable dialog window function keys	Disabled
---------------------	---------	------------------------	----------	-------------------------------------	----------

Alarms

Controller alarms

Buffer overflow	10 %	Acknowledgment group text	QGR	Use alarm class color	Disabled
Use help texts for system diagnostics	Enabled	System event duration	2 Seconds	PersistentAlarmBuffer	Enabled
Connection	HMI_Connection_1				

User administration

Enable limit for logon attempts	Enabled	Invalid logon attempts	3	Logon with password	Disabled
Group-specific rights	Disabled	Password aging	Disabled	Validity period	90
Warning period	7	Password generations	3	At least one special character	Disabled
At least one number	Disabled	Minimum password length	3		

Language & font

Preset runtime language	English (United States)
-------------------------	-------------------------

English (United States)

Runtime language	Enabled	Fixed font 1	Tahoma	Default font	Tahoma, 11 Pixel
Configured font 1					

Tag settings

Replace the separators on each sub-level of the path of the PLC tag:	Enabled	Compatibility mode: Set '_' between the PLC tags and the first-level element.	Disabled	Replace the '.' character if the name of the HMI tag is created from the PLC tag name	Enabled
Use '_' as the replacement character	Enabled	Use ';' as the replacement character	Disabled	Replace the characters '[' and ']' if the name of the HMI tag is created from the PLC tag name	Enabled
Use '{' and '}' as replacement characters	Enabled	Use '(' and ')' as replacement characters	Disabled		


Settings for the prefix 'PLC' in the HMI tag name

Connection	HMI_Connection_1	PLC name as prefix in the HMI tag name	Disabled
------------	------------------	--	----------

ChemicalProcess / HMI_1 [KTP700 Basic PN] / Screens

Different jobs

Hardcopy of Different jobs



General					
Name	Different jobs	Background color	181, 182, 181	Grid color	0, 0, 0
Number	7	Template	Template_1	Tooltip	

Layers

Active layer	0
--------------	---

Layer_0	Enabled
Layer_1	Enabled
Layer_2	Enabled
Layer_3	Enabled
Layer_4	Enabled
Layer_5	Enabled
Layer_6	Enabled
Layer_7	Enabled
Layer_8	Enabled
Layer_9	Enabled
Layer_10	Enabled
Layer_11	Enabled
Layer_12	Enabled
Layer_13	Enabled
Layer_14	Enabled
Layer_15	Enabled
Layer_16	Enabled
Layer_17	Enabled
Layer_18	Enabled
Layer_19	Enabled
Layer_20	Enabled
Layer_21	Enabled
Layer_22	Enabled
Layer_23	Enabled
Layer_24	Enabled
Layer_25	Enabled
Layer_26	Enabled
Layer_27	Enabled
Layer_28	Enabled
Layer_29	Enabled
Layer_30	Enabled
Layer_31	Enabled

Dynamizations\Event	
Event name	Loaded

Function list\SetTag

Tag	Tag_ScreenNumber	Value	7
-----	------------------	-------	---

Online

Type	Button
------	--------

General				
Mode	Text	Hotkey	None	Text OFF Online

Totally Integrated Automation Portal							
Text ON		Online	Text list			Graphic OFF	
Graphic ON			Graphic list			Process value	
Bit number		0					
Appearance							
Background color		239, 235, 239	Background fill pattern		Vertical gradient	Corner radius (border)	3
Foreground color		49, 52, 74	Border width		1	Line style	Solid
Border color		156, 154, 165	Border background color		107, 105, 107		
Fill pattern							
Background color gradient (fill pattern)		231, 227, 231	Gradient 1 (fill pattern)		Enabled	Color gradient 1 (fill pattern)	247, 247, 247
Offset gradient 1 (fill pattern)		15	Gradient 2 (fill pattern)		Enabled	Color gradient 2 (fill pattern)	222, 215, 214
Offset gradient 2 (fill pattern)		15					
Design							
Focus width		2	Focus color		148, 182, 231		
Layout							
X position		36	Y position		146	Width	159
Height		47	Fit graphic to size		Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic		Middle	Fit object to contents		Disabled	Margin left text (layout)	0
Margin top text (layout)		0	Margin right text (layout)		0	Margin bottom text (layout)	0
Margin left graphic (layout)		0	Margin top graphic (layout)		0	Margin right graphic (layout)	0
Margin bottom graphic (layout)		0					
Text format							
Font		Tahoma, 17px	Orientation		Horizontal	Horizontal alignment of the text	Centered
Vertical alignment of the text		Middle					
Styles/Designs							
Use style/design		Disabled	Style item appearance				
Miscellaneous							
Name		Online	Layer		0 - Layer_0	Tooltip	
Security							
Authorization			Allow operator control		Enabled		
Dynamizations\Event							
Event name			Release				
Function list\SetDeviceMode							
Operating mode			Online				
Offline							
Type		Button					
General							
Mode		Text	Hotkey		None	Text OFF	Offline
Text ON		Offline	Text list			Graphic OFF	
Graphic ON			Graphic list			Process value	
Bit number		0					
Appearance							
Background color		239, 235, 239	Background fill pattern		Vertical gradient	Corner radius (border)	3
Foreground color		49, 52, 74	Border width		1	Line style	Solid
Border color		156, 154, 165	Border background color		107, 105, 107		
Fill pattern							
Background color gradient (fill pattern)		231, 227, 231	Gradient 1 (fill pattern)		Enabled	Color gradient 1 (fill pattern)	247, 247, 247
Offset gradient 1 (fill pattern)		15	Gradient 2 (fill pattern)		Enabled	Color gradient 2 (fill pattern)	222, 215, 214
Offset gradient 2 (fill pattern)		15					
Design							
Focus width		2	Focus color		148, 182, 231		
Layout							
X position		36	Y position		205	Width	159
Height		47	Fit graphic to size		Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic		Middle	Fit object to contents		Disabled	Margin left text (layout)	0
Margin top text (layout)		0	Margin right text (layout)		0	Margin bottom text (layout)	0
Margin left graphic (layout)		0	Margin top graphic (layout)		0	Margin right graphic (layout)	0
Margin bottom graphic (layout)		0					
Text format							
Font		Tahoma, 17px	Orientation		Horizontal	Horizontal alignment of the text	Centered

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Vertical alignment of the text		Middle				
Styles/Designs						
Use style/design		Disabled		Style item appearance		
Miscellaneous						
Name		Offline		Layer		0 - Layer_0
Tooltip						
Security						
Authorization				Allow operator control		Enabled

Dynamizations\Event					
Event name				Release	

Function list\SetDeviceMode					
-----------------------------	--	--	--	--	--

Operating mode				Offline	
----------------	--	--	--	---------	--

Transfer					
----------	--	--	--	--	--

Type		Button			
General					
Mode		Text		Hotkey	
Text ON		Transfer		None	
Graphic ON				Text OFF	
Bit number		0		Transfer	
				Graphic OFF	
				Process value	
Appearance					
Background color		239, 235, 239		Background fill pattern	
Foreground color		49, 52, 74		Vertical gradient	
Border color		156, 154, 165		Corner radius (border)	
				3	
				Border width	
				1	
				Line style	
				Solid	
Fill pattern					
Background color gradient (fill pattern)		231, 227, 231		Gradient 1 (fill pattern)	
Offset gradient 1 (fill pattern)		15		Enabled	
Offset gradient 2 (fill pattern)		15		Gradient 2 (fill pattern)	
				Enabled	
				Color gradient 1 (fill pattern)	
				247, 247, 247	
				Color gradient 2 (fill pattern)	
				222, 215, 214	
Design					
Focus width		2		Focus color	
				148, 182, 231	
Layout					
X position		36		Y position	
Height		47		264	
				Width	
				159	
Vertical alignment of the graphic		Middle		Fit graphic to size	
Margin top text (layout)		0		Stretch graphic	
Margin left graphic (layout)		0		Horizontal alignment of the graphic	
Margin bottom graphic (layout)		0		Centered	
				Margin left text (layout)	
				0	
				Margin right text (layout)	
				0	
				Margin bottom text (layout)	
				0	
				Margin right graphic (layout)	
				0	
Text format					
Font		Tahoma, 17px		Orientation	
Vertical alignment of the text		Middle		Horizontal	
				Horizontal alignment of the text	
				Centered	

Styles/Designs					
Use style/design		Disabled		Style item appearance	
Miscellaneous					
Name		Transfer		Layer	
Tooltip		0 - Layer_0			
Security					
Authorization				Allow operator control	
				Enabled	

Dynamizations\Event					
Event name				Release	

Function list\SetDeviceMode					
-----------------------------	--	--	--	--	--

Operating mode				Loading	
----------------	--	--	--	---------	--

Toggle language					
-----------------	--	--	--	--	--

Type		Button			
General					
Mode		Text		Hotkey	
Text ON		Toggle language		None	
Graphic ON				Text OFF	
Bit number		0		Toggle language	
				Graphic OFF	
				Process value	
Appearance					
Background color		239, 235, 239		Background fill pattern	
Foreground color		49, 52, 74		Vertical gradient	
Border color		156, 154, 165		Corner radius (border)	
				3	
				Border width	
				1	
				Line style	
				Solid	
Fill pattern					
Background color gradient (fill pattern)		231, 227, 231		Gradient 1 (fill pattern)	
				Enabled	
				Color gradient 1 (fill pattern)	
				247, 247, 247	

--	--	--

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214
Offset gradient 2 (fill pattern)	15				
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	36	Y position	323	Width	159
Height	47	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	0
Margin top text (layout)	0	Margin right text (layout)	0	Margin bottom text (layout)	0
Margin left graphic (layout)	0	Margin top graphic (layout)	0	Margin right graphic (layout)	0
Margin bottom graphic (layout)	0				
Text format					
Font	Tahoma, 17px	Orientation	Horizontal	Horizontal alignment of the text	Centered
Vertical alignment of the text	Middle				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Toggle language	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		

Dynamizations\Event	
Event name	Release

Function list\SetLanguage	
---------------------------	--

Language	Toggle
----------	--------

Stop Runtime	
--------------	--

Type	Button				
General					
Mode	Text	Hotkey	None	Text OFF	Stop Runtime
Text ON	Stop Runtime	Text list		Graphic OFF	
Graphic ON		Graphic list		Process value	
Bit number	0				
Appearance					
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	1	Line style	Solid
Border color	156, 154, 165	Border background color	107, 105, 107		
Fill pattern					
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214
Offset gradient 2 (fill pattern)	15				
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	207	Y position	146	Width	159
Height	47	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	0
Margin top text (layout)	0	Margin right text (layout)	0	Margin bottom text (layout)	0
Margin left graphic (layout)	0	Margin top graphic (layout)	0	Margin right graphic (layout)	0
Margin bottom graphic (layout)	0				
Text format					
Font	Tahoma, 17px	Orientation	Horizontal	Horizontal alignment of the text	Centered
Vertical alignment of the text	Middle				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Stop Runtime	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		


Dynamizations\Event	
Event name	Release

--	--	--

ChemicalProcess / HMI_1 [KTP700 Basic PN] / Screens

Project information

Hardcopy of Project information



General						
Name	Project information		Background color	181, 182, 181	Grid color	0, 0, 0
Number	4		Template	Template_1	Tooltip	
Layers						
Active layer	0					
Layer_0			Enabled			
Layer_1			Enabled			
Layer_2			Enabled			
Layer_3			Enabled			
Layer_4			Enabled			
Layer_5			Enabled			
Layer_6			Enabled			
Layer_7			Enabled			
Layer_8			Enabled			
Layer_9			Enabled			
Layer_10			Enabled			
Layer_11			Enabled			
Layer_12			Enabled			
Layer_13			Enabled			
Layer_14			Enabled			
Layer_15			Enabled			
Layer_16			Enabled			
Layer_17			Enabled			
Layer_18			Enabled			
Layer_19			Enabled			
Layer_20			Enabled			
Layer_21			Enabled			
Layer_22			Enabled			
Layer_23			Enabled			
Layer_24			Enabled			
Layer_25			Enabled			
Layer_26			Enabled			
Layer_27			Enabled			
Layer_28			Enabled			
Layer_29			Enabled			
Layer_30			Enabled			
Layer_31			Enabled			
Dynamizations\Event						
Event name			Loaded			
Function list\SetTag						
Tag		Tag_ScreenNumber		Value	4	
HmiScreenItemData						
Type	Text field					
General						
Text	Project name:					

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Appearance

Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	0, 0, 0	Border width	0	Line style	Double line
Border color	156, 154, 165	Border background color	231, 227, 231		

Layout

X position	35	Y position	102	Width	171
Height	28	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Disabled

Text format

Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		

Flashing

Flashing	Disabled				
----------	----------	--	--	--	--

Styles/Designs

Use style/design	Disabled	Style item appearance			
------------------	----------	-----------------------	--	--	--

Miscellaneous

Name	HmiScreenItemData	Layer	0 - Layer_0		
------	-------------------	-------	-------------	--	--

HmiScreenItemData_1

Type

Text field

General

Text	ChemicalProcess				
------	-----------------	--	--	--	--

Appearance

Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	0, 0, 0	Border width	0	Line style	Double line
Border color	156, 154, 165	Border background color	231, 227, 231		

Layout

X position	241	Y position	102	Width	524
Height	28	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Disabled

Text format

Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		

Flashing

Flashing	Disabled				
----------	----------	--	--	--	--

Styles/Designs

Use style/design	Disabled	Style item appearance			
------------------	----------	-----------------------	--	--	--

Miscellaneous

Name	HmiScreenItemData_1	Layer	0 - Layer_0		
------	---------------------	-------	-------------	--	--

HmiScreenItemData_2

Type

Text field

General

Text	Created on:				
------	-------------	--	--	--	--

Appearance

Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	0, 0, 0	Border width	0	Line style	Double line
Border color	156, 154, 165	Border background color	231, 227, 231		

Layout

X position	35	Y position	132	Width	171
Height	28	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Disabled

Text format

Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		

Flashing

Flashing	Disabled				
----------	----------	--	--	--	--

Styles/Designs

Use style/design	Disabled	Style item appearance			
------------------	----------	-----------------------	--	--	--

Miscellaneous

Name	HmiScreenItemData_2	Layer	0 - Layer_0		
------	---------------------	-------	-------------	--	--

HmiScreenItemData_3

Type

Text field

General

Text	5/25/2021 10:32:50 AM				
------	-----------------------	--	--	--	--

Appearance

Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	0, 0, 0	Border width	0	Line style	Double line
Border color	156, 154, 165	Border background color	231, 227, 231		

Layout

X position	241	Y position	132	Width	524
Height	28	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Disabled

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Text format

Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		

Flashing

Flashing	Disabled				
----------	----------	--	--	--	--

Styles/Designs

Use style/design	Disabled	Style item appearance			
------------------	----------	-----------------------	--	--	--

Miscellaneous

Name	HmiScreenItemData_3	Layer	0 - Layer_0		
------	---------------------	-------	-------------	--	--

HmiScreenItemData_4

Type

Text field

General

Text

Author:

Appearance

Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	0, 0, 0	Border width	0	Line style	Double line
Border color	156, 154, 165	Border background color	231, 227, 231		

Layout

X position	35	Y position	162	Width	171
Height	28	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Disabled

Text format

Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		

Flashing

Flashing	Disabled				
----------	----------	--	--	--	--

Styles/Designs

Use style/design	Disabled	Style item appearance			
------------------	----------	-----------------------	--	--	--

Miscellaneous

Name	HmiScreenItemData_4	Layer	0 - Layer_0		
------	---------------------	-------	-------------	--	--

HmiScreenItemData_5

Type

Text field

General

Text

mika3

Appearance

Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	0, 0, 0	Border width	0	Line style	Double line
Border color	156, 154, 165	Border background color	231, 227, 231		

Layout

X position	241	Y position	162	Width	524
Height	28	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Disabled

Text format

Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		

Flashing

Flashing	Disabled				
----------	----------	--	--	--	--

Styles/Designs

Use style/design	Disabled	Style item appearance			
------------------	----------	-----------------------	--	--	--

Miscellaneous

Name	HmiScreenItemData_5	Layer	0 - Layer_0		
------	---------------------	-------	-------------	--	--

HmiScreenItemData_6

Type

Text field

General

Text

Description:

Appearance

Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	0, 0, 0	Border width	0	Line style	Double line
Border color	156, 154, 165	Border background color	231, 227, 231		

Layout

X position	35	Y position	192	Width	171
Height	28	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Disabled

Text format

Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		

Flashing

Flashing	Disabled				
----------	----------	--	--	--	--

Styles/Designs

Use style/design	Disabled	Style item appearance			
------------------	----------	-----------------------	--	--	--

Miscellaneous

Name	HmiScreenItemData_6	Layer	0 - Layer_0		
------	---------------------	-------	-------------	--	--

--	--	--

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

HmiScreenItemData_7

Type	Text field					
General						
Text	(not configured)					
Appearance						
Background color	255, 255, 255		Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	0, 0, 0		Border width	0	Line style	Double line
Border color	156, 154, 165		Border background color	231, 227, 231		
Layout						
X position	241		Y position	192	Width	524
Height	28		Left margin	3	Top margin	2
Right margin	2		Bottom margin	2	Fit object to contents	Disabled
Text format						
Font	Tahoma, 16px, style=Bold		Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle		Line break	Disabled		
Flashing						
Flashing	Disabled					
Styles/Designs						
Use style/design	Disabled		Style item appearance			
Miscellaneous						
Name	HmiScreenItemData_7		Layer	0 - Layer_0		

Back

Type	Button						
General							
Mode	Text		Hotkey	None	Text OFF	Back	
Text ON	Back		Text list		Graphic OFF		
Graphic ON			Graphic list		Process value		
Bit number	0						
Appearance							
Background color	239, 235, 239		Background fill pattern	Vertical gradient	Corner radius (border)	3	
Foreground color	49, 52, 74		Border width	1	Line style	Solid	
Border color	156, 154, 165		Border background color	107, 105, 107			
Fill pattern							
Background color gradient (fill pattern)	231, 227, 231		Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247	
Offset gradient 1 (fill pattern)	15		Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214	
Offset gradient 2 (fill pattern)	15						
Design							
Focus width	2		Focus color	148, 182, 231			
Layout							
X position	1		Y position	52	Width	159	
Height	47		Fit graphic to size	Stretch graphic		Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle		Fit object to contents	Disabled		Margin left text (layout)	0
Margin top text (layout)	0		Margin right text (layout)	0		Margin bottom text (layout)	0
Margin left graphic (layout)	0		Margin top graphic (layout)	0		Margin right graphic (layout)	0
Margin bottom graphic (layout)	0						
Text format							
Font	Tahoma, 16px, style=Bold		Orientation	Horizontal	Horizontal alignment of the text	Centered	
Vertical alignment of the text	Middle						
Styles/Designs							
Use style/design	Disabled		Style item appearance				
Miscellaneous							
Name	Back		Layer	0 - Layer_0		Tooltip	
Security							
Authorization			Allow operator control	Enabled			

Dynamizations\Event

Event name	Release	
------------	---------	--


Function list\ActivateScreen

Screen name	System screens		Object number	0	
-------------	----------------	--	---------------	---	--

ChemicalProcess / HMI_1 [KTP700 Basic PN] / Screens

Root screen

Hardcopy of Root screen



General					
Name	Root screen	Background color	181, 182, 181	Grid color	0, 0, 0
Number	1	Template	Template_1	Tooltip	
Layers					
Active layer	0				
Layer_0			Enabled		
Layer_1			Enabled		
Layer_2			Enabled		
Layer_3			Enabled		
Layer_4			Enabled		
Layer_5			Enabled		
Layer_6			Enabled		
Layer_7			Enabled		
Layer_8			Enabled		
Layer_9			Enabled		
Layer_10			Enabled		
Layer_11			Enabled		
Layer_12			Enabled		
Layer_13			Enabled		
Layer_14			Enabled		
Layer_15			Enabled		
Layer_16			Enabled		
Layer_17			Enabled		
Layer_18			Enabled		
Layer_19			Enabled		
Layer_20			Enabled		
Layer_21			Enabled		
Layer_22			Enabled		
Layer_23			Enabled		
Layer_24			Enabled		
Layer_25			Enabled		
Layer_26			Enabled		
Layer_27			Enabled		
Layer_28			Enabled		
Layer_29			Enabled		
Layer_30			Enabled		
Layer_31			Enabled		
Dynamizations\Event					
Event name		Loaded			
Function list\SetTag					
Tag	Tag_ScreenNumber		Value	1	
HmiScreenItemData_1					
Type	Button				
General					
Mode	Graphics and text	Hotkey	None	Text OFF	System screens

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Text ON	System screens	Text list		Graphic OFF	Navigates to System screens for KTP700 Basic+ PN 16.0.0.0
Graphic ON	Navigates to System screens for KTP700 Basic+ PN 16.0.0.0	Graphic list		Process value	
Bit number	0				
Appearance					
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	1	Line style	Solid
Border color	156, 154, 165	Border background color	107, 105, 107		
Fill pattern					
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214
Offset gradient 2 (fill pattern)	15				
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	623	Y position	67	Width	159
Height	47	Fit graphic to size	No stretching of graphic	Horizontal alignment of the graphic	Left
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	48
Margin top text (layout)	5	Margin right text (layout)	5	Margin bottom text (layout)	5
Margin left graphic (layout)	5	Margin top graphic (layout)	5	Margin right graphic (layout)	5
Margin bottom graphic (layout)	5				
Text format					
Font	Tahoma, 12px	Orientation	Horizontal	Horizontal alignment of the text	Left
Vertical alignment of the text	Middle				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	HmiScreenItemData_1	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		

Dynamizations\Event	
Event name	Release

Function list\ActivateScreen	
------------------------------	--

Screen name	System screens	Object number	0
-------------	----------------	---------------	---

I/O field_1	
-------------	--

Type	I/O field
------	-----------

General					
Process value		Mode	Input/output	Display format	Decimal
Shift decimal point	0	Field length	3	Show leading zeros	Disabled
Format pattern	s999				
Appearance					
Background color	255, 255, 255	Background fill pattern	Solid	Corner radius	3
Foreground color	49, 52, 74	Unit		Border width	4
Line style	Double line	Border color	66, 73, 82	Border background color	99, 101, 115
Characteristics					
Hidden input	Disabled				
Layout					
X position	120	Y position	129	Width	96
Height	32	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Disabled
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		
Limits					
Color for High limit violated	239, 89, 99	Color for Low limit violated	247, 162, 41		
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	I/O field_1	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		

Dynamizations\Tag connection			
Property name	Process value	Tag	WT-512

--	--	--

Totally Integrated Automation Portal						
Text field_1						
Type	Text field					
General						
Text	WI-512					
Appearance						
Background color	255, 255, 255		Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	49, 52, 74		Border width	0	Line style	Double line
Border color	66, 73, 82		Border background color	99, 101, 115		
Layout						
X position	42		Y position	137	Width	65
Height	23		Left margin	3	Top margin	2
Right margin	2		Bottom margin	2	Fit object to contents	Enabled
Text format						
Font	Tahoma, 16px, style=Bold		Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle		Line break	Disabled		
Flashing						
Flashing	Disabled					
Styles/Designs						
Use style/design	Disabled		Style item appearance			
Miscellaneous						
Name	Text field_1		Layer	0 - Layer_0		
Switch_1						
Type	Switch					
General						
Process value			Value status ON	1	Mode	Switch
Text ON	ON		Text OFF	OFF	Graphic ON	
Graphic OFF						
Appearance						
Foreground color	90, 89, 107		Background color	99, 101, 115	Inner background color ON	247, 243, 247
Inner background color OFF	247, 243, 247		Border width	2	Line style	Solid
Border color	66, 73, 82		Border background color	107, 105, 107	Corner radius	3
Fill pattern						
Background fill pattern	Vertical gradient		Background color gradient (fill pattern)	99, 101, 115	Gradient 1 (fill pattern)	Enabled
Color gradient 1 (fill pattern)	132, 134, 140		Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled
Color gradient 2 (fill pattern)	90, 89, 99		Offset gradient 2 (fill pattern)	15		
Design						
Focus width	2		Focus color	148, 182, 231		
Layout						
X position	357		Y position	120	Width	64
Height	32		Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle		Switch orientation	Left to right	Fit object to contents	Disabled
Margin left text (layout)	0		Margin top text (layout)	0	Margin right text (layout)	0
Margin bottom text (layout)	0		Margin left graphic (layout)	0	Margin top graphic (layout)	0
Margin right graphic (layout)	0		Margin bottom graphic (layout)	0		
Text format						
Font	Tahoma, 16px, style=Bold		Orientation	Horizontal	Horizontal alignment of the text	Centered
Vertical alignment of the text	Middle					
Limits						
Color for High limit violated	239, 97, 99		Color for Low limit violated	255, 219, 41		
Styles/Designs						
Use style/design	Disabled		Style item appearance			
Miscellaneous						
Name	Switch_1		Layer	0 - Layer_0	Tooltip	
Security						
Authorization			Allow operator control	Enabled		
Dynamizations\Tag connection						
Property name	Process value		Tag	GSV-510		
Text field_3						
Type	Text field					
General						
Text						
Appearance						
Background color	255, 255, 255		Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	49, 52, 74		Border width	0	Line style	Double line

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Border color	66, 73, 82	Border background color	99, 101, 115		
Layout					
X position	283	Y position	122	Width	16
Height	23	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Enabled
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		
Flashing					
Flashing	Disabled				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Text field_3	Layer	0 - Layer_0		

Text field_2

Type	Text field				
General					
Text	GSV-510				
Appearance					
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	0	Line style	Double line
Border color	66, 73, 82	Border background color	99, 101, 115		
Layout					
X position	277	Y position	122	Width	75
Height	23	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Enabled
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		
Flashing					
Flashing	Disabled				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Text field_2	Layer	0 - Layer_0		

Switch_2

Type	Switch				
General					
Process value		Value status ON	1	Mode	Switch
Text ON	ON	Text OFF	OFF	Graphic ON	
Graphic OFF					
Appearance					
Foreground color	90, 89, 107	Background color	99, 101, 115	Inner background color ON	247, 243, 247
Inner background color OFF	247, 243, 247	Border width	2	Line style	Solid
Border color	66, 73, 82	Border background color	107, 105, 107	Corner radius	3
Fill pattern					
Background fill pattern	Vertical gradient	Background color gradient (fill pattern)	99, 101, 115	Gradient 1 (fill pattern)	Enabled
Color gradient 1 (fill pattern)	132, 134, 140	Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled
Color gradient 2 (fill pattern)	90, 89, 99	Offset gradient 2 (fill pattern)	15		
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	357	Y position	168	Width	64
Height	32	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle	Switch orientation	Left to right	Fit object to contents	Disabled
Margin left text (layout)	0	Margin top text (layout)	0	Margin right text (layout)	0
Margin bottom text (layout)	0	Margin left graphic (layout)	0	Margin top graphic (layout)	0
Margin right graphic (layout)	0	Margin bottom graphic (layout)	0		
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered
Vertical alignment of the text	Middle				
Limits					
Color for High limit violated	239, 97, 99	Color for Low limit violated	255, 219, 41		
Styles/Designs					
Use style/design	Disabled	Style item appearance			

--	--	--

Totally Integrated Automation Portal						
Miscellaneous						
Name	Switch_2	Layer	0 - Layer_0	Tooltip		
Security						
Authorization		Allow operator control	Enabled			
Dynamizations\Tag connection						
Property name	Process value	Tag	GSV-511			
Text field_4						
Type	Text field					
General						
Text	GSV-511					
Appearance						
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3	
Foreground color	49, 52, 74	Border width	0	Line style	Double line	
Border color	66, 73, 82	Border background color	99, 101, 115			
Layout						
X position	277	Y position	170	Width	75	
Height	23	Left margin	3	Top margin	2	
Right margin	2	Bottom margin	2	Fit object to contents	Enabled	
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle	Line break	Disabled			
Flashing						
Flashing	Disabled					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Text field_4	Layer	0 - Layer_0			
Switch_3						
Type	Switch					
General						
Process value		Value status ON	1	Mode	Switch	
Text ON	ON	Text OFF	OFF	Graphic ON		
Graphic OFF						
Appearance						
Foreground color	90, 89, 107	Background color	99, 101, 115	Inner background color ON	247, 243, 247	
Inner background color OFF	247, 243, 247	Border width	2	Line style	Solid	
Border color	66, 73, 82	Border background color	107, 105, 107	Corner radius	3	
Fill pattern						
Background fill pattern	Vertical gradient	Background color gradient (fill pattern)	99, 101, 115	Gradient 1 (fill pattern)	Enabled	
Color gradient 1 (fill pattern)	132, 134, 140	Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	
Color gradient 2 (fill pattern)	90, 89, 99	Offset gradient 2 (fill pattern)	15			
Design						
Focus width	2	Focus color	148, 182, 231			
Layout						
X position	361	Y position	216	Width	64	
Height	32	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered	
Vertical alignment of the graphic	Middle	Switch orientation	Left to right	Fit object to contents	Disabled	
Margin left text (layout)	0	Margin top text (layout)	0	Margin right text (layout)	0	
Margin bottom text (layout)	0	Margin left graphic (layout)	0	Margin top graphic (layout)	0	
Margin right graphic (layout)	0	Margin bottom graphic (layout)	0			
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered	
Vertical alignment of the text	Middle					
Limits						
Color for High limit violated	239, 97, 99	Color for Low limit violated	255, 219, 41			
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Switch_3	Layer	0 - Layer_0	Tooltip		
Security						
Authorization		Allow operator control	Enabled			
Dynamization\Tag connection						
Property name	Process value	Tag	GSV-514			

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Text field_5

Type	Text field				
General					
Text					
Appearance					
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	0	Line style	Double line
Border color	66, 73, 82	Border background color	99, 101, 115		
Layout					
X position	287	Y position	218	Width	16
Height	23	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Enabled
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		
Flashing					
Flashing	Disabled				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Text field_5	Layer	0 - Layer_0		

Text field_6

Type	Text field				
General					
Text		GSV-514			
Appearance					
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	0	Line style	Double line
Border color	66, 73, 82	Border background color	99, 101, 115		
Layout					
X position	281	Y position	218	Width	75
Height	23	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Enabled
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		
Flashing					
Flashing	Disabled				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Text field_6	Layer	0 - Layer_0		

Switch_4

Type	Switch				
General					
Process value		Value status ON	1	Mode	Switch
Text ON	ON	Text OFF	OFF	Graphic ON	
Graphic OFF					
Appearance					
Foreground color	90, 89, 107	Background color	99, 101, 115	Inner background color ON	247, 243, 247
Inner background color OFF	247, 243, 247	Border width	2	Line style	Solid
Border color	66, 73, 82	Border background color	107, 105, 107	Corner radius	3
Fill pattern					
Background fill pattern	Vertical gradient	Background color gradient (fill pattern)	99, 101, 115	Gradient 1 (fill pattern)	Enabled
Color gradient 1 (fill pattern)	132, 134, 140	Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled
Color gradient 2 (fill pattern)	90, 89, 99	Offset gradient 2 (fill pattern)	15		
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	361	Y position	264	Width	64
Height	32	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle	Switch orientation	Left to right	Fit object to contents	Disabled
Margin left text (layout)	0	Margin top text (layout)	0	Margin right text (layout)	0
Margin bottom text (layout)	0	Margin left graphic (layout)	0	Margin top graphic (layout)	0
Margin right graphic (layout)	0	Margin bottom graphic (layout)	0		

--	--	--

Totally Integrated Automation Portal						
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered	
Vertical alignment of the text	Middle					
Limits						
Color for High limit violated	239, 97, 99	Color for Low limit violated	255, 219, 41			
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Switch_4	Layer	0 - Layer_0	Tooltip		
Security						
Authorization		Allow operator control	Enabled			
Dynamizations\Tag connection						
Property name	Process value	Tag	GSV-519			
Text field_7						
Type	Text field					
General						
Text	GSV-519					
Appearance						
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3	
Foreground color	49, 52, 74	Border width	0	Line style	Double line	
Border color	66, 73, 82	Border background color	99, 101, 115			
Layout						
X position	281	Y position	266	Width	75	
Height	23	Left margin	3	Top margin	2	
Right margin	2	Bottom margin	2	Fit object to contents	Enabled	
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle	Line break	Disabled			
Flashing						
Flashing	Disabled					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Text field_7	Layer	0 - Layer_0			
Switch_5						
Type	Switch					
General						
Process value		Value status ON	1	Mode	Switch	
Text ON	ON	Text OFF	OFF	Graphic ON		
Graphic OFF						
Appearance						
Foreground color	90, 89, 107	Background color	99, 101, 115	Inner background color ON	247, 243, 247	
Inner background color OFF	247, 243, 247	Border width	2	Line style	Solid	
Border color	66, 73, 82	Border background color	107, 105, 107	Corner radius	3	
Fill pattern						
Background fill pattern	Vertical gradient	Background color gradient (fill pattern)	99, 101, 115	Gradient 1 (fill pattern)	Enabled	
Color gradient 1 (fill pattern)	132, 134, 140	Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	
Color gradient 2 (fill pattern)	90, 89, 99	Offset gradient 2 (fill pattern)	15			
Design						
Focus width	2	Focus color	148, 182, 231			
Layout						
X position	361	Y position	312	Width	64	
Height	32	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered	
Vertical alignment of the graphic	Middle	Switch orientation	Left to right	Fit object to contents	Disabled	
Margin left text (layout)	0	Margin top text (layout)	0	Margin right text (layout)	0	
Margin bottom text (layout)	0	Margin left graphic (layout)	0	Margin top graphic (layout)	0	
Margin right graphic (layout)	0	Margin bottom graphic (layout)	0			
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered	
Vertical alignment of the text	Middle					
Limits						
Color for High limit violated	239, 97, 99	Color for Low limit violated	255, 219, 41			

Totally Integrated Automation Portal						
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Switch_5	Layer	0 - Layer_0	Tooltip		
Security						
Authorization		Allow operator control	Enabled			
Dynamizations\Tag connection						
Property name	Process value	Tag	GSV-521			
Text field_8						
Type	Text field					
General						
Text	GSV-521					
Appearance						
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3	
Foreground color	49, 52, 74	Border width	0	Line style	Double line	
Border color	66, 73, 82	Border background color	99, 101, 115			
Layout						
X position	281	Y position	314	Width	75	
Height	23	Left margin	3	Top margin	2	
Right margin	2	Bottom margin	2	Fit object to contents	Enabled	
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle	Line break	Disabled			
Flashing						
Flashing	Disabled					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Text field_8	Layer	0 - Layer_0			
Switch_6						
Type	Switch					
General						
Process value		Value status ON	1	Mode	Switch	
Text ON	ON	Text OFF	OFF	Graphic ON		
Graphic OFF						
Appearance						
Foreground color	90, 89, 107	Background color	99, 101, 115	Inner background color ON	247, 243, 247	
Inner background color OFF	247, 243, 247	Border width	2	Line style	Solid	
Border color	66, 73, 82	Border background color	107, 105, 107	Corner radius	3	
Fill pattern						
Background fill pattern	Vertical gradient	Background color gradient (fill pattern)	99, 101, 115	Gradient 1 (fill pattern)	Enabled	
Color gradient 1 (fill pattern)	132, 134, 140	Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	
Color gradient 2 (fill pattern)	90, 89, 99	Offset gradient 2 (fill pattern)	15			
Design						
Focus width	2	Focus color	148, 182, 231			
Layout						
X position	529	Y position	163	Width	64	
Height	32	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered	
Vertical alignment of the graphic	Middle	Switch orientation	Left to right	Fit object to contents	Disabled	
Margin left text (layout)	0	Margin top text (layout)	0	Margin right text (layout)	0	
Margin bottom text (layout)	0	Margin left graphic (layout)	0	Margin top graphic (layout)	0	
Margin right graphic (layout)	0	Margin bottom graphic (layout)	0			
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered	
Vertical alignment of the text	Middle					
Limits						
Color for High limit violated	239, 97, 99	Color for Low limit violated	255, 219, 41			
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Switch_6	Layer	0 - Layer_0	Tooltip		
Security						
Authorization		Allow operator control	Enabled			
Dynamizations\Tag connection						
Property name	Process value	Tag	"M001.ST"			

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Text field_9

Type	Text field				
General					
Text	M001				
Appearance					
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	0	Line style	Double line
Border color	66, 73, 82	Border background color	99, 101, 115		
Layout					
X position	478	Y position	168	Width	49
Height	23	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Enabled
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		
Flashing					
Flashing	Disabled				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Text field_9	Layer	0 - Layer_0		

Switch_7

Type	Switch				
General					
Process value		Value status ON	1	Mode	Switch
Text ON	ON	Text OFF	OFF	Graphic ON	
Graphic OFF					
Appearance					
Foreground color	90, 89, 107	Background color	99, 101, 115	Inner background color ON	247, 243, 247
Inner background color OFF	247, 243, 247	Border width	2	Line style	Solid
Border color	66, 73, 82	Border background color	107, 105, 107	Corner radius	3
Fill pattern					
Background fill pattern	Vertical gradient	Background color gradient (fill pattern)	99, 101, 115	Gradient 1 (fill pattern)	Enabled
Color gradient 1 (fill pattern)	132, 134, 140	Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled
Color gradient 2 (fill pattern)	90, 89, 99	Offset gradient 2 (fill pattern)	15		
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	536	Y position	296	Width	64
Height	32	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle	Switch orientation	Left to right	Fit object to contents	Disabled
Margin left text (layout)	0	Margin top text (layout)	0	Margin right text (layout)	0
Margin bottom text (layout)	0	Margin left graphic (layout)	0	Margin top graphic (layout)	0
Margin right graphic (layout)	0	Margin bottom graphic (layout)	0		
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered
Vertical alignment of the text	Middle				
Limits					
Color for High limit violated	239, 97, 99	Color for Low limit violated	255, 219, 41		
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Switch_7	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		
Dynamizations\Tag connection					
Property name	Process value	Tag	"M003.ST"		

Text field_10

Type	Text field				
General					
Text	M003				
Appearance					
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	0	Line style	Double line

--	--	--

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Border color	66, 73, 82	Border background color	99, 101, 115		
Layout					
X position	470	Y position	296	Width	49
Height	23	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Enabled
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		
Flashing					
Flashing	Disabled				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Text field_10	Layer	0 - Layer_0		

Switch_8

Type	Switch				
General					
Process value		Value status ON	1	Mode	Switch
Text ON	ON	Text OFF	OFF	Graphic ON	
Graphic OFF					
Appearance					
Foreground color	90, 89, 107	Background color	99, 101, 115	Inner background color ON	247, 243, 247
Inner background color OFF	247, 243, 247	Border width	2	Line style	Solid
Border color	66, 73, 82	Border background color	107, 105, 107	Corner radius	3
Fill pattern					
Background fill pattern	Vertical gradient	Background color gradient (fill pattern)	99, 101, 115	Gradient 1 (fill pattern)	Enabled
Color gradient 1 (fill pattern)	132, 134, 140	Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled
Color gradient 2 (fill pattern)	90, 89, 99	Offset gradient 2 (fill pattern)	15		
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	536	Y position	221	Width	64
Height	32	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle	Switch orientation	Left to right	Fit object to contents	Disabled
Margin left text (layout)	0	Margin top text (layout)	0	Margin right text (layout)	0
Margin bottom text (layout)	0	Margin left graphic (layout)	0	Margin top graphic (layout)	0
Margin right graphic (layout)	0	Margin bottom graphic (layout)	0		
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered
Vertical alignment of the text	Middle				
Limits					
Color for High limit violated	239, 97, 99	Color for Low limit violated	255, 219, 41		
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Switch_8	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		
Dynamizations\Tag connection					
Property name	Process value	Tag	"M002.ST"		

Text field_11

Type	Text field				
General					
Text	M002				
Appearance					
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	0	Line style	Double line
Border color	66, 73, 82	Border background color	99, 101, 115		
Layout					
X position	470	Y position	225	Width	49
Height	23	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Enabled
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		

--	--	--

Totally Integrated Automation Portal							
Flashing							
Flashing	Disabled						
Styles/Designs							
Use style/design	Disabled		Style item appearance				
Miscellaneous							
Name	Text field_11		Layer	0 - Layer_0			
I/O field_4							
Type	I/O field						
General							
Process value			Mode	Input/output		Display format	Decimal
Shift decimal point	0		Field length	3		Show leading zeros	Disabled
Format pattern	s999						
Appearance							
Background color	255, 255, 255		Background fill pattern	Solid		Corner radius	3
Foreground color	49, 52, 74		Unit			Border width	4
Line style	Double line		Border color	66, 73, 82		Border background color	99, 101, 115
Characteristics							
Hidden input	Disabled						
Layout							
X position	120		Y position	170		Width	96
Height	32		Left margin	3		Top margin	2
Right margin	2		Bottom margin	2		Fit object to contents	Disabled
Text format							
Font	Tahoma, 16px, style=Bold		Orientation	Horizontal		Horizontal alignment	Left
Vertical alignment	Middle		Line break	Disabled			
Limits							
Color for High limit violated	239, 89, 99		Color for Low limit violated	247, 162, 41			
Styles/Designs							
Use style/design	Disabled		Style item appearance				
Miscellaneous							
Name	I/O field_4		Layer	0 - Layer_0		Tooltip	
Security							
Authorization			Allow operator control	Enabled			
Dynamizations\Tag connection							
Property name	Process value		Tag	TT-517			
Text field_14							
Type	Text field						
General							
Text	TT-517						
Appearance							
Background color	255, 255, 255		Background fill pattern	Transparent		Corner radius (border)	3
Foreground color	49, 52, 74		Border width	0		Line style	Double line
Border color	66, 73, 82		Border background color	99, 101, 115			
Layout							
X position	45		Y position	177		Width	64
Height	23		Left margin	3		Top margin	2
Right margin	2		Bottom margin	2		Fit object to contents	Enabled
Text format							
Font	Tahoma, 16px, style=Bold		Orientation	Horizontal		Horizontal alignment	Left
Vertical alignment	Middle		Line break	Disabled			
Flashing							
Flashing	Disabled						
Styles/Designs							
Use style/design	Disabled		Style item appearance				
Miscellaneous							
Name	Text field_14		Layer	0 - Layer_0			
I/O field_5							
Type	I/O field						
General							
Process value			Mode	Input/output		Display format	Decimal
Shift decimal point	0		Field length	3		Show leading zeros	Disabled
Format pattern	s999						
Appearance							
Background color	255, 255, 255		Background fill pattern	Solid		Corner radius	3
Foreground color	49, 52, 74		Unit			Border width	4
Line style	Double line		Border color	66, 73, 82		Border background color	99, 101, 115
Characteristics							
Hidden input	Disabled						
Layout							
X position	120		Y position	209		Width	96
Height	32		Left margin	3		Top margin	2
Right margin	2		Bottom margin	2		Fit object to contents	Disabled

Totally Integrated Automation Portal						
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle	Line break	Disabled			
Limits						
Color for High limit violated	239, 89, 99	Color for Low limit violated	247, 162, 41			
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	I/O field_5	Layer	0 - Layer_0	Tooltip		
Security						
Authorization		Allow operator control	Enabled			
Dynamizations\Tag connection						
Property name	Process value	Tag	TT-518			
Text field_15						
Type	Text field					
General						
Text	TT-518					
Appearance						
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3	
Foreground color	49, 52, 74	Border width	0	Line style	Double line	
Border color	66, 73, 82	Border background color	99, 101, 115			
Layout						
X position	42	Y position	214	Width	64	
Height	23	Left margin	3	Top margin	2	
Right margin	2	Bottom margin	2	Fit object to contents	Enabled	
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle	Line break	Disabled			
Flashing						
Flashing	Disabled					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Text field_15	Layer	0 - Layer_0			
Circle_1						
Type	Circle					
Appearance						
Background color	49, 154, 99	Background fill pattern	Solid	Border width	1	
Line style	Solid	Border color	24, 28, 49			
Layout						
X position	623	Y position	154	Width	48	
Height	48	Radius	24			
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Circle_1	Layer	0 - Layer_0			
Dynamizations\Visibility						
Tag - Cycle	"M001.R" -	Data type	Range	Start range	1	
End range	1	Visibility	Visible			
Circle_2						
Type	Circle					
Appearance						
Background color	49, 154, 99	Background fill pattern	Solid	Border width	1	
Line style	Solid	Border color	24, 28, 49			
Layout						
X position	623	Y position	215	Width	48	
Height	48	Radius	24			
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Circle_2	Layer	0 - Layer_0			
Dynamizations\Visibility						
Tag - Cycle	"M002.R" -	Data type	Range	Start range	1	
End range	1	Visibility	Visible			
Circle_3						
Type	Circle					
Appearance						
Background color	49, 154, 99	Background fill pattern	Solid	Border width	1	
Line style	Solid	Border color	24, 28, 49			

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Layout

X position	623	Y position	276	Width	48
Height	48	Radius	24		

Styles/Designs

Use style/design	Disabled	Style item appearance			
------------------	----------	-----------------------	--	--	--

Miscellaneous

Name	Circle_3	Layer	0 - Layer_0		
------	----------	-------	-------------	--	--

Dynamizations\Visibility

Tag - Cycle	"M003.R" -	Data type	Range	Start range	1
End range	1	Visibility	Visible		

Bar_1

Type

Bar

General

Maximum value	27648	Minimum value	0	Process value	0
---------------	-------	---------------	---	---------------	---

Appearance

Foreground color	0, 121, 206	Segment coloring	Entire bar	Background color	247, 243, 247
Background fill pattern	Solid	Color of scale	49, 52, 74	Limit lines (layout)	Enabled
Limit marking (layout)	Enabled				

Border type

Border width	7	Border color	66, 73, 82	Border background color	99, 101, 115
Line style	Double line	Corner radius (border)	4		

Scales

Show scale	Disabled	Auto-scale	Disabled	Divisions	5
Large mark labeling	1	Scale gradation	100		

Label

Show scale marks	Enabled	Show "+" for positive numbers	Disabled	Use exponential format	Disabled
Double-lined scale label	Disabled	Unit		Integer digits	5
Decimal places	0				

Layout

X position	50	Y position	253	Width	80
Height	120	Scale position	Left/up	Bar orientation	Top

Text format

Font	Tahoma, 13px, style=Bold				
------	--------------------------	--	--	--	--

Limits/Ranges

Color range high 2	239, 89, 99	Color range low 2	247, 162, 41		
--------------------	-------------	-------------------	--------------	--	--

Styles/Designs

Use style/design	Disabled	Style item appearance			
------------------	----------	-----------------------	--	--	--

Miscellaneous

Name	Bar_1	Layer	0 - Layer_0		
------	-------	-------	-------------	--	--

Dynamizations\Tag connection

Property name	Process value	Tag	LT-515		
---------------	---------------	-----	--------	--	--

Text field_12

Type

Text field

General

Text	LT-515				
------	--------	--	--	--	--

Appearance

Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	0	Line style	Double line
Border color	66, 73, 82	Border background color	99, 101, 115		

Layout

X position	141	Y position	268	Width	62
Height	23	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Enabled

Text format

Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left
Vertical alignment	Middle	Line break	Disabled		

Flashing

Flashing	Disabled				
----------	----------	--	--	--	--

Styles/Designs

Use style/design	Disabled	Style item appearance			
------------------	----------	-----------------------	--	--	--

Miscellaneous

Name	Text field_12	Layer	0 - Layer_0		
------	---------------	-------	-------------	--	--

I/O field_2

Type

I/O field

General

Process value		Mode	Input/output	Display format	Decimal
Shift decimal point	0	Field length	3	Show leading zeros	Disabled
Format pattern	s999				

Appearance


Background color	255, 255, 255	Background fill pattern	Solid	Corner radius	3
Foreground color	49, 52, 74	Unit		Border width	4

Totally Integrated Automation Portal						
Line style	Double line	Border color	66, 73, 82	Border background color	99, 101, 115	
Characteristics						
Hidden input	Disabled					
Layout						
X position	134	Y position	296	Width	96	
Height	32	Left margin	3	Top margin	2	
Right margin	2	Bottom margin	2	Fit object to contents	Disabled	
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle	Line break	Disabled			
Limits						
Color for High limit violated	239, 89, 99	Color for Low limit violated	247, 162, 41			
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	I/O field_2	Layer	0 - Layer_0	Tooltip		
Security						
Authorization		Allow operator control	Enabled			
Dynamizations\Tag connection						
Property name	Process value	Tag	LT-515			

ChemicalProcess / HMI_1 [KTP700 Basic PN] / Screens

SIMATIC PLC system diagnostics

Hardcopy of SIMATIC PLC system diagnostics



General					
Name	SIMATIC PLC system diagnostics	Background color	181, 182, 181	Grid color	0, 0, 0
Number	3	Template	Template_1	Tooltip	
Layers					
Active layer	0				
Layer_0			Enabled		
Layer_1			Enabled		
Layer_2			Enabled		
Layer_3			Enabled		
Layer_4			Enabled		
Layer_5			Enabled		
Layer_6			Enabled		
Layer_7			Enabled		
Layer_8			Enabled		
Layer_9			Enabled		
Layer_10			Enabled		
Layer_11			Enabled		
Layer_12			Enabled		
Layer_13			Enabled		
Layer_14			Enabled		
Layer_15			Enabled		
Layer_16			Enabled		
Layer_17			Enabled		
Layer_18			Enabled		
Layer_19			Enabled		
Layer_20			Enabled		
Layer_21			Enabled		
Layer_22			Enabled		
Layer_23			Enabled		
Layer_24			Enabled		
Layer_25			Enabled		
Layer_26			Enabled		
Layer_27			Enabled		
Layer_28			Enabled		
Layer_29			Enabled		
Layer_30			Enabled		
Layer_31			Enabled		
Dynamizations\Event					
Event name		Loaded			
Function list\SetTag					
Tag	Tag_ScreenNumber		Value	3	
HmiScreenItemData					
Type	System diagnostics view				

Totally Integrated Automation Portal

Back

Type

Button

General

Mode

Text

Hotkey

None

Text OFF

Back

Text ON

Back

Text list

Graphic OFF

Graphic ON

Graphic list

Process value

Bit number

0

Appearance

Background color

239, 235, 239

Background fill pattern

Vertical gradient

Corner radius (border)

3

Foreground color

49, 52, 74

Border width

1

Line style

Solid

Border color

156, 154, 165

Border background color

107, 105, 107

Fill pattern

Background color gradient (fill pattern)

231, 227, 231

Gradient 1 (fill pattern)

Enabled

Color gradient 1 (fill pattern)

247, 247, 247

Offset gradient 1 (fill pattern)

15

Gradient 2 (fill pattern)

Enabled

Color gradient 2 (fill pattern)

222, 215, 214

Offset gradient 2 (fill pattern)

15

Design

Focus width

2

Focus color

148, 182, 231

Layout

X position

1

Y position

52

Width

159

Height

47

Fit graphic to size

Stretch graphic

Horizontal alignment of the graphic

Centered

Vertical alignment of the graphic

Middle

Fit object to contents

Disabled

Margin left text (layout)

0

Margin top text (layout)

0

Margin right text (layout)

0

Margin bottom text (layout)

0

Margin left graphic (layout)

0

Margin top graphic (layout)

0

Margin right graphic (layout)

0

Margin bottom graphic (layout)

0

Text format

Font

Tahoma, 16px, style=Bold

Orientation

Horizontal

Horizontal alignment of the text

Centered

Vertical alignment of the text

Middle

Styles/Designs

Use style/design

Disabled

Style item appearance

Miscellaneous

Name

Back

Layer

0 - Layer_0

Tooltip

Security

Authorization

Allow operator control

Enabled

Dynamizations\Event

Event name

Release

Function list\ActivateScreen

Screen name

System screens


Object number

0

ChemicalProcess / HMI_1 [KTP700 Basic PN] / Screens

System information

Hardcopy of System information



General					
Name	System information	Background color	181, 182, 181	Grid color	0, 0, 0
Number	6	Template	Template_1	Tooltip	
Layers					
Active layer	0				
Layer_0			Enabled		
Layer_1			Enabled		
Layer_2			Enabled		
Layer_3			Enabled		
Layer_4			Enabled		
Layer_5			Enabled		
Layer_6			Enabled		
Layer_7			Enabled		
Layer_8			Enabled		
Layer_9			Enabled		
Layer_10			Enabled		
Layer_11			Enabled		
Layer_12			Enabled		
Layer_13			Enabled		
Layer_14			Enabled		
Layer_15			Enabled		
Layer_16			Enabled		
Layer_17			Enabled		
Layer_18			Enabled		
Layer_19			Enabled		
Layer_20			Enabled		
Layer_21			Enabled		
Layer_22			Enabled		
Layer_23			Enabled		
Layer_24			Enabled		
Layer_25			Enabled		
Layer_26			Enabled		
Layer_27			Enabled		
Layer_28			Enabled		
Layer_29			Enabled		
Layer_30			Enabled		
Layer_31			Enabled		
Dynamizations\Event					
Event name		Loaded			
Function list\SetTag					
Tag	Tag_ScreenNumber		Value	6	
HmiScreenItemData					
Type	Text field				
General					
Text	HMI device type:				


Totally Integrated Automation Portal						
Appearance						
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3	
Foreground color	0, 0, 0	Border width	0	Line style	Double line	
Border color	156, 154, 165	Border background color	231, 227, 231			
Layout						
X position	35	Y position	102	Width	171	
Height	28	Left margin	3	Top margin	2	
Right margin	2	Bottom margin	2	Fit object to contents	Disabled	
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle	Line break	Disabled			
Flashing						
Flashing	Disabled					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	HmiScreenItemData	Layer	0 - Layer_0			
HmiScreenItemData_1						
Type	Text field					
General						
Text	KTP700 Basic+ PN 16.0.0.0					
Appearance						
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3	
Foreground color	0, 0, 0	Border width	0	Line style	Double line	
Border color	156, 154, 165	Border background color	231, 227, 231			
Layout						
X position	241	Y position	102	Width	524	
Height	28	Left margin	3	Top margin	2	
Right margin	2	Bottom margin	2	Fit object to contents	Disabled	
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle	Line break	Disabled			
Flashing						
Flashing	Disabled					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	HmiScreenItemData_1	Layer	0 - Layer_0			
HmiScreenItemData_2						
Type	Text field					
General						
Text	Connection:					
Appearance						
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3	
Foreground color	0, 0, 0	Border width	0	Line style	Double line	
Border color	156, 154, 165	Border background color	231, 227, 231			
Layout						
X position	35	Y position	132	Width	171	
Height	28	Left margin	3	Top margin	2	
Right margin	2	Bottom margin	2	Fit object to contents	Disabled	
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle	Line break	Disabled			
Flashing						
Flashing	Disabled					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	HmiScreenItemData_2	Layer	0 - Layer_0			
HmiScreenItemData_3						
Type	Text field					
General						
Text	PROFINET (X1)					
Appearance						
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3	
Foreground color	0, 0, 0	Border width	0	Line style	Double line	
Border color	156, 154, 165	Border background color	231, 227, 231			
Layout						
X position	241	Y position	132	Width	524	
Height	28	Left margin	3	Top margin	2	
Right margin	2	Bottom margin	2	Fit object to contents	Disabled	

Totally Integrated Automation Portal						
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle	Line break	Disabled			
Flashing						
Flashing	Disabled					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	HmiScreenItemData_3	Layer	0 - Layer_0			
HmiScreenItemData_4						
Type	Text field					
General						
Text	PLC:					
Appearance						
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3	
Foreground color	0, 0, 0	Border width	0	Line style	Double line	
Border color	156, 154, 165	Border background color	231, 227, 231			
Layout						
X position	35	Y position	162	Width	171	
Height	28	Left margin	3	Top margin	2	
Right margin	2	Bottom margin	2	Fit object to contents	Disabled	
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle	Line break	Disabled			
Flashing						
Flashing	Disabled					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	HmiScreenItemData_4	Layer	0 - Layer_0			
HmiScreenItemData_5						
Type	Text field					
General						
Text	SIMATIC S7 1500					
Appearance						
Background color	255, 255, 255	Background fill pattern	Transparent	Corner radius (border)	3	
Foreground color	0, 0, 0	Border width	0	Line style	Double line	
Border color	156, 154, 165	Border background color	231, 227, 231			
Layout						
X position	241	Y position	162	Width	524	
Height	28	Left margin	3	Top margin	2	
Right margin	2	Bottom margin	2	Fit object to contents	Disabled	
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle	Line break	Disabled			
Flashing						
Flashing	Disabled					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	HmiScreenItemData_5	Layer	0 - Layer_0			
Back						
Type	Button					
General						
Mode	Text	Hotkey	None	Text OFF	Back	
Text ON	Back	Text list		Graphic OFF		
Graphic ON		Graphic list		Process value		
Bit number	0					
Appearance						
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3	
Foreground color	49, 52, 74	Border width	1	Line style	Solid	
Border color	156, 154, 165	Border background color	107, 105, 107			
Fill pattern						
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247	
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214	
Offset gradient 2 (fill pattern)	15					
Design						
Focus width	2	Focus color	148, 182, 231			
Layout						
X position	1	Y position	52	Width	159	

ChemicalProcess / HMI_1 [KTP700 Basic PN] / Screens

System screens

Hardcopy of System screens



General					
Name	System screens	Background color	181, 182, 181	Grid color	0, 0, 0
Number	2	Template	Template_1	Tooltip	

Layers	
Active layer	0

Layer_0	Enabled
Layer_1	Enabled
Layer_2	Enabled
Layer_3	Enabled
Layer_4	Enabled
Layer_5	Enabled
Layer_6	Enabled
Layer_7	Enabled
Layer_8	Enabled
Layer_9	Enabled
Layer_10	Enabled
Layer_11	Enabled
Layer_12	Enabled
Layer_13	Enabled
Layer_14	Enabled
Layer_15	Enabled
Layer_16	Enabled
Layer_17	Enabled
Layer_18	Enabled
Layer_19	Enabled
Layer_20	Enabled
Layer_21	Enabled
Layer_22	Enabled
Layer_23	Enabled
Layer_24	Enabled
Layer_25	Enabled
Layer_26	Enabled
Layer_27	Enabled
Layer_28	Enabled
Layer_29	Enabled
Layer_30	Enabled
Layer_31	Enabled

Dynamizations\Event	
Event name	Loaded

Function list\SetTag	
----------------------	--

Tag	Tag_ScreenNumber	Value	2
-----	------------------	-------	---

Back	
------	--

Type	Button
------	--------

General			
Mode	Text	Hotkey	None
Text OFF	Back		

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Text ON	Back	Text list		Graphic OFF	
Graphic ON		Graphic list		Process value	
Bit number	0				
Appearance					
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	1	Line style	Solid
Border color	156, 154, 165	Border background color	107, 105, 107		
Fill pattern					
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214
Offset gradient 2 (fill pattern)	15				
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	1	Y position	52	Width	159
Height	47	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	0
Margin top text (layout)	0	Margin right text (layout)	0	Margin bottom text (layout)	0
Margin left graphic (layout)	0	Margin top graphic (layout)	0	Margin right graphic (layout)	0
Margin bottom graphic (layout)	0				
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered
Vertical alignment of the text	Middle				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Back	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		

Dynamizations\Event	
Event name	Release

Function list\ActivateScreen	
------------------------------	--

Screen name	Root screen	Object number	0
-------------	-------------	---------------	---

HmiScreenItemData	
-------------------	--

Type	Button				
General					
Mode	Graphics and text	Hotkey	None	Text OFF	SIMATIC PLC system diagnos...
Text ON	SIMATIC PLC system diagnos...	Text list		Graphic OFF	Navigates to SIMATIC PLC system diagnostics for KTP700 Basic+ PN 16.0.0.0
Graphic ON	Navigates to SIMATIC PLC system diagnostics for KTP700 Basic+ PN 16.0.0.0	Graphic list		Process value	
Bit number	0				
Appearance					
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	1	Line style	Solid
Border color	156, 154, 165	Border background color	107, 105, 107		
Fill pattern					
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214
Offset gradient 2 (fill pattern)	15				
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	36	Y position	146	Width	159
Height	47	Fit graphic to size	No stretching of graphic	Horizontal alignment of the graphic	Left
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	48
Margin top text (layout)	5	Margin right text (layout)	5	Margin bottom text (layout)	5
Margin left graphic (layout)	5	Margin top graphic (layout)	5	Margin right graphic (layout)	5
Margin bottom graphic (layout)	5				

--	--	--

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Text format

Font	Tahoma, 12px	Orientation	Horizontal	Horizontal alignment of the text	Left
Vertical alignment of the text	Middle				

Styles/Designs

Use style/design	Disabled	Style item appearance			
------------------	----------	-----------------------	--	--	--

Miscellaneous

Name	HmiScreenItemData	Layer	0 - Layer_0	Tooltip	
------	-------------------	-------	-------------	---------	--

Security

Authorization		Allow operator control	Enabled		
---------------	--	------------------------	---------	--	--

Dynamizations\Event

Event name	Release				
------------	---------	--	--	--	--

Function list\ActivateScreen

Screen name	SIMATIC PLC system diagnostics		Object number	0	
-------------	--------------------------------	--	---------------	---	--

HmiScreenItemData_1

Type	Button				
General					
Mode	Graphics and text	Hotkey	None	Text OFF	Project information
Text ON	Project information	Text list		Graphic OFF	Navigates to Project information for KTP700 Basic+ PN 16.0.0.0
Graphic ON	Navigates to Project information for KTP700 Basic+ PN 16.0.0.0	Graphic list		Process value	
Bit number	0				
Appearance					
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	1	Line style	Solid
Border color	156, 154, 165	Border background color	107, 105, 107		
Fill pattern					
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214
Offset gradient 2 (fill pattern)	15				
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	36	Y position	205	Width	159
Height	47	Fit graphic to size	No stretching of graphic	Horizontal alignment of the graphic	Left
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	48
Margin top text (layout)	5	Margin right text (layout)	5	Margin bottom text (layout)	5
Margin left graphic (layout)	5	Margin top graphic (layout)	5	Margin right graphic (layout)	5
Margin bottom graphic (layout)	5				
Text format					
Font	Tahoma, 12px	Orientation	Horizontal	Horizontal alignment of the text	Left
Vertical alignment of the text	Middle				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	HmiScreenItemData_1	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		

Dynamizations\Event

Event name	Release				
------------	---------	--	--	--	--

Function list\ActivateScreen

Screen name	Project information		Object number	0	
-------------	---------------------	--	---------------	---	--

HmiScreenItemData_2

Type	Button				
General					
Mode	Graphics and text	Hotkey	None	Text OFF	User administration
Text ON	User administration	Text list		Graphic OFF	Navigates to User administration for KTP700 Basic+ PN 16.0.0.0
Graphic ON	Navigates to User administration for KTP700 Basic+ PN 16.0.0.0	Graphic list		Process value	
Bit number	0				


--	--	--	--	--	--

Totally Integrated Automation Portal						
Appearance						
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3	
Foreground color	49, 52, 74	Border width	1	Line style	Solid	
Border color	156, 154, 165	Border background color	107, 105, 107			
Fill pattern						
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247	
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214	
Offset gradient 2 (fill pattern)	15					
Design						
Focus width	2	Focus color	148, 182, 231			
Layout						
X position	36	Y position	264	Width	159	
Height	47	Fit graphic to size	No stretching of graphic	Horizontal alignment of the graphic	Left	
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	48	
Margin top text (layout)	5	Margin right text (layout)	5	Margin bottom text (layout)	5	
Margin left graphic (layout)	5	Margin top graphic (layout)	5	Margin right graphic (layout)	5	
Margin bottom graphic (layout)	5					
Text format						
Font	Tahoma, 12px	Orientation	Horizontal	Horizontal alignment of the text	Left	
Vertical alignment of the text	Middle					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	HmiScreenItemData_2	Layer	0 - Layer_0	Tooltip		
Security						
Authorization		Allow operator control	Enabled			
Dynamizations\Event						
Event name		Release				
Function list\ActivateScreen						
Screen name		User administration		Object number	0	
HmiScreenItemData_3						
Type	Button					
General						
Mode	Graphics and text	Hotkey	None	Text OFF	System information	
Text ON	System information	Text list		Graphic OFF	Navigates to System information for KTP700 Basic+ PN 16.0.0.0	
Graphic ON	Navigates to System information for KTP700 Basic+ PN 16.0.0.0	Graphic list		Process value		
Bit number	0					
Appearance						
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3	
Foreground color	49, 52, 74	Border width	1	Line style	Solid	
Border color	156, 154, 165	Border background color	107, 105, 107			
Fill pattern						
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247	
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214	
Offset gradient 2 (fill pattern)	15					
Design						
Focus width	2	Focus color	148, 182, 231			
Layout						
X position	36	Y position	323	Width	159	
Height	47	Fit graphic to size	No stretching of graphic	Horizontal alignment of the graphic	Left	
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	48	
Margin top text (layout)	5	Margin right text (layout)	5	Margin bottom text (layout)	5	
Margin left graphic (layout)	5	Margin top graphic (layout)	5	Margin right graphic (layout)	5	
Margin bottom graphic (layout)	5					
Text format						
Font	Tahoma, 12px	Orientation	Horizontal	Horizontal alignment of the text	Left	
Vertical alignment of the text	Middle					

ChemicalProcess / HMI_1 [KTP700 Basic PN] / Screens

User administration

Hardcopy of User administration




General					
Name	User administration	Background color	181, 182, 181	Grid color	0, 0, 0
Number	5	Template	Template_1	Tooltip	
Layers					
Active layer	0				
Layer_0			Enabled		
Layer_1			Enabled		
Layer_2			Enabled		
Layer_3			Enabled		
Layer_4			Enabled		
Layer_5			Enabled		
Layer_6			Enabled		
Layer_7			Enabled		
Layer_8			Enabled		
Layer_9			Enabled		
Layer_10			Enabled		
Layer_11			Enabled		
Layer_12			Enabled		
Layer_13			Enabled		
Layer_14			Enabled		
Layer_15			Enabled		
Layer_16			Enabled		
Layer_17			Enabled		
Layer_18			Enabled		
Layer_19			Enabled		
Layer_20			Enabled		
Layer_21			Enabled		
Layer_22			Enabled		
Layer_23			Enabled		
Layer_24			Enabled		
Layer_25			Enabled		
Layer_26			Enabled		
Layer_27			Enabled		
Layer_28			Enabled		
Layer_29			Enabled		
Layer_30			Enabled		
Layer_31			Enabled		
Dynamizations\Event					
Event name		Loaded			
Function list\SetTag					
Tag	Tag_ScreenNumber		Value	5	
HmiScreenItemData					
Type	User view				

Totally Integrated Automation Portal						
Appearance						
Table foreground color	49, 52, 74	Background color of table	255, 255, 255	Alternative color	231, 231, 239	
Header foreground color	49, 52, 74	Header background color	239, 235, 239	Foreground color of selection	49, 52, 74	
Background color of selection	148, 182, 231					
Border						
Width (border)	1	Style (border)	Solid	Foreground color (border)	99, 105, 115	
Background color (border)	99, 105, 115	Corner radius (border)	4			
Layout						
X position	1	Y position	100	Width	796	
Height	321	Fit object to contents	Disabled			
Columns						
User	156	Password	402	Group	80	
Logoff time	120					
Display						
Background color	231, 223, 222	Grid color	255, 255, 255	Number of visible items	8	
Display table grid	Enabled					
Table header border						
Width (table header border)	1	Style (table header border)	Solid	Color (table header border)	156, 154, 165	
Background color (table header border)	156, 154, 165	Corner radius (table header border)	2			
Table header fill pattern						
Fill pattern (table header fill pattern)	Vertical gradient	Background color gradient (table header fill pattern)	239, 235, 239	Gradient 1 (table header fill pattern)	Enabled	
Color gradient 1 (table header fill pattern)	247, 247, 247	Offset gradient 1 (table header fill pattern)	15	Gradient 2 (table header fill pattern)	Enabled	
Color gradient 2 (table header fill pattern)	231, 223, 222	Offset gradient 2 (table header fill pattern)	15			
Text format						
Table font	Tahoma, 15px	Table header font	Tahoma, 15px, style=Bold			
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	HmiScreenItemData	Layer	0 - Layer_0			
Security						
Allow operator control	Enabled					
Back						
Type	Button					
General						
Mode	Text	Hotkey	None	Text OFF	Back	
Text ON	Back	Text list		Graphic OFF		
Graphic ON		Graphic list		Process value		
Bit number	0					
Appearance						
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3	
Foreground color	49, 52, 74	Border width	1	Line style	Solid	
Border color	156, 154, 165	Border background color	107, 105, 107			
Fill pattern						
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247	
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214	
Offset gradient 2 (fill pattern)	15					
Design						
Focus width	2	Focus color	148, 182, 231			
Layout						
X position	1	Y position	52	Width	159	
Height	47	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered	
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	0	
Margin top text (layout)	0	Margin right text (layout)	0	Margin bottom text (layout)	0	
Margin left graphic (layout)	0	Margin top graphic (layout)	0	Margin right graphic (layout)	0	
Margin bottom graphic (layout)	0					
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered	
Vertical alignment of the text	Middle					

ChemicalProcess / HMI_1 [KTP700 Basic PN] / Screen management / Templates

Template_1

Hardcopy of Template_1



General					
Name	Template_1	Background color	181, 182, 181	Grid color	0, 0, 0

Tab sequence in foreground	Enabled
----------------------------	---------

Layers

Active layer	0
--------------	---

Layer_0	Enabled
Layer_1	Enabled
Layer_2	Enabled
Layer_3	Enabled
Layer_4	Enabled
Layer_5	Enabled
Layer_6	Enabled
Layer_7	Enabled
Layer_8	Enabled
Layer_9	Enabled
Layer_10	Enabled
Layer_11	Enabled
Layer_12	Enabled
Layer_13	Enabled
Layer_14	Enabled
Layer_15	Enabled
Layer_16	Enabled
Layer_17	Enabled
Layer_18	Enabled
Layer_19	Enabled
Layer_20	Enabled
Layer_21	Enabled
Layer_22	Enabled
Layer_23	Enabled
Layer_24	Enabled
Layer_25	Enabled
Layer_26	Enabled
Layer_27	Enabled
Layer_28	Enabled
Layer_29	Enabled
Layer_30	Enabled
Layer_31	Enabled

Exit

Type	Button
------	--------

General					
Mode	Graphic	Hotkey	None	Text OFF	Exit
Text ON	Exit	Text list		Graphic OFF	ExitRuntime_KTP700_Basic_PN_TR
Graphic ON	ExitRuntime_KTP700_Basic_PN_TR	Graphic list		Process value	
Bit number	0				

Totally Integrated Automation Portal						
Appearance						
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3	
Foreground color	49, 52, 74	Border width	1	Line style	Solid	
Border color	156, 154, 165	Border background color	107, 105, 107			
Fill pattern						
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247	
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214	
Offset gradient 2 (fill pattern)	15					
Design						
Focus width	2	Focus color	148, 182, 231			
Layout						
X position	714	Y position	429	Width	71	
Height	50	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered	
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	0	
Margin top text (layout)	0	Margin right text (layout)	0	Margin bottom text (layout)	0	
Margin left graphic (layout)	0	Margin top graphic (layout)	0	Margin right graphic (layout)	0	
Margin bottom graphic (layout)	0					
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered	
Vertical alignment of the text	Middle					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Exit	Layer	0 - Layer_0	Tooltip		
Security						
Authorization		Allow operator control	Enabled			
Dynamizations\Event						
Event name		Release				
Function list\StopRuntime						
Mode		Runtime				
Language						
Type	Button					
General						
Mode	Graphic	Hotkey	None	Text OFF	Language	
Text ON	Language	Text list		Graphic OFF	ToggleLanguage_KTP700_Basic_PN_TR	
Graphic ON	ToggleLanguage_KTP700_Basic_PN_TR	Graphic list		Process value		
Bit number	0					
Appearance						
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3	
Foreground color	49, 52, 74	Border width	1	Line style	Solid	
Border color	156, 154, 165	Border background color	107, 105, 107			
Fill pattern						
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247	
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214	
Offset gradient 2 (fill pattern)	15					
Design						
Focus width	2	Focus color	148, 182, 231			
Layout						
X position	614	Y position	429	Width	71	
Height	50	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered	
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	0	
Margin top text (layout)	0	Margin right text (layout)	0	Margin bottom text (layout)	0	
Margin left graphic (layout)	0	Margin top graphic (layout)	0	Margin right graphic (layout)	0	
Margin bottom graphic (layout)	0					
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered	
Vertical alignment of the text	Middle					

Totally Integrated Automation Portal						
Styles/Designs						
Use style/design	Disabled		Style item appearance			
Miscellaneous						
Name	Language	Layer	0 - Layer_0		Tooltip	
Security						
Authorization			Allow operator control	Enabled		
Dynamizations\Event						
Event name			Release			
Function list\SetLanguage						
Language			Toggle			
Template_Button						
Type	Button					
General						
Mode	Text		Hotkey	None		Text OFF
Text ON			Text list			Graphic OFF
Graphic ON			Graphic list			Process value
Bit number	0					
Appearance						
Background color	239, 235, 239		Background fill pattern	Vertical gradient		Corner radius (border)
Foreground color	49, 52, 74		Border width	1		Line style
Border color	156, 154, 165		Border background color	107, 105, 107		Solid
Fill pattern						
Background color gradient (fill pattern)	231, 227, 231		Gradient 1 (fill pattern)	Enabled		Color gradient 1 (fill pattern)
Offset gradient 1 (fill pattern)	15		Gradient 2 (fill pattern)	Enabled		Color gradient 2 (fill pattern)
Offset gradient 2 (fill pattern)	15					
Design						
Focus width	2		Focus color	148, 182, 231		
Layout						
X position	514		Y position	429		Width
Height	50		Fit graphic to size	Stretch graphic		Horizontal alignment of the graphic
Vertical alignment of the graphic	Middle		Fit object to contents	Disabled		Margin left text (layout)
Margin top text (layout)	0		Margin right text (layout)	0		Margin bottom text (layout)
Margin left graphic (layout)	0		Margin top graphic (layout)	0		Margin right graphic (layout)
Margin bottom graphic (layout)	0					
Text format						
Font	Tahoma, 16px, style=Bold		Orientation	Horizontal		Horizontal alignment of the text
Vertical alignment of the text	Middle					
Styles/Designs						
Use style/design	Disabled		Style item appearance			
Miscellaneous						
Name	Template_Button		Layer	0 - Layer_0		Tooltip
Security						
Authorization			Allow operator control	Enabled		
Template_Button_1						
Type	Button					
General						
Mode	Text		Hotkey	None		Text OFF
Text ON			Text list			Graphic OFF
Graphic ON			Graphic list			Process value
Bit number	0					
Appearance						
Background color	239, 235, 239		Background fill pattern	Vertical gradient		Corner radius (border)
Foreground color	49, 52, 74		Border width	1		Line style
Border color	156, 154, 165		Border background color	107, 105, 107		Solid
Fill pattern						
Background color gradient (fill pattern)	231, 227, 231		Gradient 1 (fill pattern)	Enabled		Color gradient 1 (fill pattern)
Offset gradient 1 (fill pattern)	15		Gradient 2 (fill pattern)	Enabled		Color gradient 2 (fill pattern)
Offset gradient 2 (fill pattern)	15					
Design						
Focus width	2		Focus color	148, 182, 231		
Layout						
X position	414		Y position	429		Width

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Height	50	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	0
Margin top text (layout)	0	Margin right text (layout)	0	Margin bottom text (layout)	0
Margin left graphic (layout)	0	Margin top graphic (layout)	0	Margin right graphic (layout)	0
Margin bottom graphic (layout)	0				
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered
Vertical alignment of the text	Middle				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Template_Button_1	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		

Template_Button_2

Type	Button				
General					
Mode	Text	Hotkey	None	Text OFF	
Text ON		Text list		Graphic OFF	
Graphic ON		Graphic list		Process value	
Bit number	0				
Appearance					
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	1	Line style	Solid
Border color	156, 154, 165	Border background color	107, 105, 107		
Fill pattern					
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214
Offset gradient 2 (fill pattern)	15				
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	314	Y position	429	Width	71
Height	50	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	0
Margin top text (layout)	0	Margin right text (layout)	0	Margin bottom text (layout)	0
Margin left graphic (layout)	0	Margin top graphic (layout)	0	Margin right graphic (layout)	0
Margin bottom graphic (layout)	0				
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered
Vertical alignment of the text	Middle				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Template_Button_2	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		

Template_Button_3

Type	Button				
General					
Mode	Text	Hotkey	None	Text OFF	
Text ON		Text list		Graphic OFF	
Graphic ON		Graphic list		Process value	
Bit number	0				
Appearance					
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	1	Line style	Solid
Border color	156, 154, 165	Border background color	107, 105, 107		
Fill pattern					
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247

--	--	--	--	--	--

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214
Offset gradient 2 (fill pattern)	15				
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	214	Y position	429	Width	71
Height	50	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	0
Margin top text (layout)	0	Margin right text (layout)	0	Margin bottom text (layout)	0
Margin left graphic (layout)	0	Margin top graphic (layout)	0	Margin right graphic (layout)	0
Margin bottom graphic (layout)	0				
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered
Vertical alignment of the text	Middle				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Template_Button_3	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		

Alarms

Type	Button				
General					
Mode	Graphic	Hotkey	None	Text OFF	Alarms
Text ON	Alarms	Text list		Graphic OFF	AlarmDisplay_KTP700_Basic_PN_TR
Graphic ON	AlarmDisplay_KTP700_Basic_PN_TR	Graphic list		Process value	
Bit number	0				
Appearance					
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3
Foreground color	49, 52, 74	Border width	1	Line style	Solid
Border color	156, 154, 165	Border background color	107, 105, 107		
Fill pattern					
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214
Offset gradient 2 (fill pattern)	15				
Design					
Focus width	2	Focus color	148, 182, 231		
Layout					
X position	114	Y position	429	Width	71
Height	50	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	0
Margin top text (layout)	0	Margin right text (layout)	0	Margin bottom text (layout)	0
Margin left graphic (layout)	0	Margin top graphic (layout)	0	Margin right graphic (layout)	0
Margin bottom graphic (layout)	0				
Text format					
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered
Vertical alignment of the text	Middle				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	Alarms	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		

Dynamizations\Event

Event name	Release
------------	---------

Function list\ShowAlarmWindow

Object name	Alarm window_Unacknowledged	Display mode	Toggle
-------------	-----------------------------	--------------	--------

Start screen

Type	Button
------	--------

Totally Integrated Automation Portal						
General						
Mode	Graphic	Hotkey	None	Text OFF	Start screen	
Text ON	Start screen	Text list		Graphic OFF	NavigateHome_KTP700_Basic_PN_TR	
Graphic ON	NavigateHome_KTP700_Basic_PN_TR	Graphic list		Process value		
Bit number	0					
Appearance						
Background color	239, 235, 239	Background fill pattern	Vertical gradient	Corner radius (border)	3	
Foreground color	49, 52, 74	Border width	1	Line style	Solid	
Border color	156, 154, 165	Border background color	107, 105, 107			
Fill pattern						
Background color gradient (fill pattern)	231, 227, 231	Gradient 1 (fill pattern)	Enabled	Color gradient 1 (fill pattern)	247, 247, 247	
Offset gradient 1 (fill pattern)	15	Gradient 2 (fill pattern)	Enabled	Color gradient 2 (fill pattern)	222, 215, 214	
Offset gradient 2 (fill pattern)	15					
Design						
Focus width	2	Focus color	148, 182, 231			
Layout						
X position	14	Y position	429	Width	71	
Height	50	Fit graphic to size	Stretch graphic	Horizontal alignment of the graphic	Centered	
Vertical alignment of the graphic	Middle	Fit object to contents	Disabled	Margin left text (layout)	0	
Margin top text (layout)	0	Margin right text (layout)	0	Margin bottom text (layout)	0	
Margin left graphic (layout)	0	Margin top graphic (layout)	0	Margin right graphic (layout)	0	
Margin bottom graphic (layout)	0					
Text format						
Font	Tahoma, 16px, style=Bold	Orientation	Horizontal	Horizontal alignment of the text	Centered	
Vertical alignment of the text	Middle					
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Start screen	Layer	0 - Layer_0	Tooltip		
Security						
Authorization		Allow operator control	Enabled			
Dynamizations\Event						
Event name		Release				
Function list\ActivateScreen						
Screen name		Root screen	Object number		0	
Symbolic_IO_Field_Screen						
Type	Symbolic I/O field					
General						
Process value	0	Bit number	0	Mode	Input/output	
Value status ON	1	Text OFF	0	Text ON	1	
Text list	TextList_ScreenNames	Number of visible items	3			
Appearance						
Background color	255, 255, 255	Background fill pattern	Solid	Corner radius (border)	3	
Foreground color	49, 52, 74	Border width	1	Line style	Solid	
Border color	156, 154, 165	Border background color	231, 227, 231			
Design						
Foreground color of selection	255, 255, 255	Background color of selection	165, 207, 214	Alternative color	231, 231, 239	
Layout						
X position	93	Y position	9	Width	600	
Height	33	Left margin	3	Top margin	2	
Right margin	2	Bottom margin	2	Fit object to contents	Disabled	
Display selection list	Enabled	Show selection field	Enabled			
Text format						
Font	Tahoma, 20px	Orientation	Horizontal	Horizontal alignment	Left	
Vertical alignment	Middle					
Limits						
Color for High limit violated	239, 89, 99	Color for Low limit violated	247, 162, 41			
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Symbolic_IO_Field_Screen	Layer	0 - Layer_0	Tooltip		
Security						
Authorization		Allow operator control	Enabled			

Totally Integrated Automation Portal						
--------------------------------------	--	--	--	--	--	--

Dynamizations\Tag connection

Property name	Process value	Tag	Tag_ScreenNumber		
---------------	---------------	-----	------------------	--	--

Dynamizations\Event

Event name	Change				
------------	--------	--	--	--	--

Function list\ActivateScreenByNumber

Screen number	Tag_ScreenNumber	Object number	0		
---------------	------------------	---------------	---	--	--

HmiScreenItemData

Type	Date/time field				
General					
Display system time	Enabled	Process value		Show date	Disabled
Show time	Enabled	Mode	Output		
Appearance					
Foreground color	0, 0, 0	Background color	255, 255, 255	Background fill pattern	Transparent
Corner radius (border)	3	Border width	0	Line style	Double line
Border color	156, 154, 165	Border background color	231, 227, 231		
Layout					
X position	695	Y position	25	Width	105
Height	25	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Disabled
Text format					
Font	Tahoma, 16px	Orientation	Horizontal	Horizontal alignment	Right
Vertical alignment	Middle				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	HmiScreenItemData	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		

HmiScreenItemData_1

Type	Date/time field				
General					
Display system time	Enabled	Process value		Show date	Enabled
Show time	Disabled	Mode	Output		
Appearance					
Foreground color	0, 0, 0	Background color	255, 255, 255	Background fill pattern	Transparent
Corner radius (border)	3	Border width	0	Line style	Double line
Border color	156, 154, 165	Border background color	231, 227, 231		
Layout					
X position	695	Y position	0	Width	105
Height	25	Left margin	3	Top margin	2
Right margin	2	Bottom margin	2	Fit object to contents	Disabled
Text format					
Font	Tahoma, 16px	Orientation	Horizontal	Horizontal alignment	Right
Vertical alignment	Middle				
Styles/Designs					
Use style/design	Disabled	Style item appearance			
Miscellaneous					
Name	HmiScreenItemData_1	Layer	0 - Layer_0	Tooltip	
Security					
Authorization		Allow operator control	Enabled		

Logo


Type	Graphic view				
General					
Graphic	Logo of HMI_1				
Appearance					
Background color	222, 219, 222	Background fill pattern	Transparent	Border width	0
Line style	Solid	Border color	0, 0, 0		
Layout					
X position	0	Y position	0	Width	91
Height	51	Fit embedded graphic object to screen size	Fit graphic to object size	Fit graphic to size	Stretch graphic
Fit object to contents	Disabled				
Miscellaneous					
Name	Logo	Layer	0 - Layer_0		

--	--	--

ChemicalProcess / HMI_1 [KTP700 Basic PN] / Screen management

Global screen

Hardcopy of Global screen



General					
Name	Global screen	Background color	181, 182, 181	Grid color	0, 0, 0
Alarm window_Unacknowledged					
Type	Alarm window				
General					
Alarm classes	Errors	Source of alarms	Alarms	Pending alarms	Disabled
Unacknowledged alarms	Enabled				
Appearance					
Background color of table	255, 255, 255	Alternative color	231, 231, 239	Foreground color of table	49, 52, 74
Foreground color of selection	255, 255, 255	Background color of selection	148, 182, 231	Background color	247, 243, 247
Focus color	148, 182, 231	Header foreground color	49, 52, 74	Header background color	239, 235, 239
Color of the grid lines	255, 255, 255				
Layout					
X position	25	Y position	25	Width	700
Height	380	Fit object to contents	Disabled	Lines per alarms	1
Visible alarms	1				
Window					
Display automatically	Enabled	Modal dialog	Disabled	Enabled	Enabled
Title	Unacknowledged alarms	Close button	Enabled		
Display					
Vertical scrolling	Enabled	Horizontal scrolling	Disabled	Horizontal grid lines	Disabled
Focus width	2				
Text format					
Table font	Tahoma, 15px	Table header font	Tahoma, 15px, style=Bold		
Toolbar					
"Info text" button	Enabled	Acknowledge button	Enabled	Loop-In-Alarm button	Disabled
Toolbar style	Buttons				
Button border					
Width (button border)	1	Style (button border)	Solid	Foreground color (button border)	156, 154, 165
Background color (button border)	156, 154, 165	Corner radius (button border)	3		
Button fill pattern					
Fill pattern (button fill pattern)	Vertical gradient	Background color (button fill pattern)	239, 235, 239	Background color gradient (button fill pattern)	239, 235, 239
Gradient 1 (button fill pattern)	Enabled	Color gradient 1 (button fill pattern)	247, 247, 247	Offset gradient 1 (button fill pattern)	15
Gradient 2 (button fill pattern)	Enabled	Color gradient 2 (button fill pattern)	231, 223, 222	Offset gradient 2 (button fill pattern)	15
Columns					
Columns	Alarm number, Time, Alarm text, Date, Alarm class	Column headers	Enabled	Time in milliseconds	Disabled
Time sorting order	Descending				

Totally Integrated Automation Portal						
Column headers						
Alarm number	Default value	Time	Default value	Alarm status	Default value	
Alarm text	Default value	Alarm class	Default value	Date	Default value	
Acknowledgment group	Default value	Diagnosable	Default value	PLC (error location)	Default value	
Table header border						
Width (table header border)	1	Style (table header border)	Solid	Color (table header border)	156, 154, 165	
Background color (table header border)	156, 154, 165	Corner radius (table header border)	2			
Table header fill pattern						
Fill pattern (table header fill pattern)	Vertical gradient	Background color gradient (table header fill pattern)	239, 235, 239	Gradient 1 (table header fill pattern)	Enabled	
Color gradient 1 (table header fill pattern)	247, 247, 247	Offset gradient 1 (table header fill pattern)	15	Gradient 2 (table header fill pattern)	Enabled	
Color gradient 2 (table header fill pattern)	231, 223, 222	Offset gradient 2 (table header fill pattern)	15			
Styles/Designs						
Use style/design	Disabled	Style item appearance				
Miscellaneous						
Name	Alarm window_Unacknowledged					
Alarm window_Pending						
Type	Alarm window					
General						
Alarm classes	Errors	Source of alarms	Alarms	Pending alarms	Enabled	
Unacknowledged alarms	Disabled					
Appearance						
Background color of table	255, 255, 255	Alternative color	231, 231, 239	Foreground color of table	49, 52, 74	
Foreground color of selection	255, 255, 255	Background color of selection	148, 182, 231	Background color	247, 243, 247	
Focus color	148, 182, 231	Header foreground color	49, 52, 74	Header background color	239, 235, 239	
Color of the grid lines	255, 255, 255					
Layout						
X position	50	Y position	50	Width	700	
Height	380	Fit object to contents	Disabled	Lines per alarms	1	
Visible alarms	1					
Window						
Display automatically	Enabled	Modal dialog	Disabled	Enabled	Enabled	
Title	Pending alarms	Close button	Enabled			
Display						
Vertical scrolling	Enabled	Horizontal scrolling	Disabled	Horizontal grid lines	Disabled	
Focus width	2					
Text format						
Table font	Tahoma, 15px	Table header font	Tahoma, 15px, style=Bold			
Toolbar						
"Info text" button	Enabled	Acknowledge button	Enabled	Loop-In-Alarm button	Disabled	
Toolbar style	Buttons					
Button border						
Width (button border)	1	Style (button border)	Solid	Foreground color (button border)	156, 154, 165	
Background color (button border)	156, 154, 165	Corner radius (button border)	3			
Button fill pattern						
Fill pattern (button fill pattern)	Vertical gradient	Background color (button fill pattern)	239, 235, 239	Background color gradient (button fill pattern)	239, 235, 239	
Gradient 1 (button fill pattern)	Enabled	Color gradient 1 (button fill pattern)	247, 247, 247	Offset gradient 1 (button fill pattern)	15	
Gradient 2 (button fill pattern)	Enabled	Color gradient 2 (button fill pattern)	231, 223, 222	Offset gradient 2 (button fill pattern)	15	
Columns						
Columns	Alarm number, Time, Alarm text, Date, Alarm class	Column headers	Enabled	Time in milliseconds	Disabled	
Time sorting order	Descending					
Column headers						
Alarm number	Default value	Time	Default value	Alarm status	Default value	
Alarm text	Default value	Alarm class	Default value	Date	Default value	
Acknowledgment group	Default value	Diagnosable	Default value	PLC (error location)	Default value	
Table header border						
Width (table header border)	1	Style (table header border)	Solid	Color (table header border)	156, 154, 165	
Background color (table header border)	156, 154, 165	Corner radius (table header border)	2			
Table header fill pattern						
Fill pattern (table header fill pattern)	Vertical gradient	Background color gradient (table header fill pattern)	239, 235, 239	Gradient 1 (table header fill pattern)	Enabled	
Color gradient 1 (table header fill pattern)	247, 247, 247	Offset gradient 1 (table header fill pattern)	15	Gradient 2 (table header fill pattern)	Enabled	

Totally Integrated Automation Portal							
Color gradient 2 (table header fill pattern)		231, 223, 222		Offset gradient 2 (table header fill pattern)		15	
Styles/Designs							
Use style/design		Disabled		Style item appearance			
Miscellaneous							
Name		Alarm window_Pending					
Alarm indicator							
Type		Alarm indicator					
Layout							
X position		740			Y position		51
General							
Display alarm classes		Acknowledged : Errors Pending : Errors					
Dynamizations\Event							
Event name				Click			
Function list\ShowAlarmWindow							
Object name		Alarm window_Pending			Display mode		Toggle
Dynamizations\Event							
Event name				Click when flashing			
Function list\ShowAlarmWindow							
Object name		Alarm window_Pending			Display mode		Toggle
System events							
Type		Alarm window					
General							
Alarm classes		System		Source of alarms		Alarms	Pending alarms Enabled
Unacknowledged alarms		Disabled					
Appearance							
Background color of table		255, 255, 255		Alternative color		231, 231, 239	Foreground color of table 49, 52, 74
Foreground color of selection		255, 255, 255		Background color of selection		148, 182, 231	Background color 247, 243, 247
Focus color		148, 182, 231		Header foreground color		49, 52, 74	Header background color 239, 235, 239
Color of the grid lines		255, 255, 255					
Layout							
X position		75		Y position		75	Width 700
Height		380		Fit object to contents		Disabled	Lines per alarms 1
Visible alarms		1					
Window							
Display automatically		Enabled		Modal dialog		Disabled	Enabled Enabled
Title		Active system events		Close button		Enabled	
Display							
Vertical scrolling		Enabled		Horizontal scrolling		Disabled	Horizontal grid lines Disabled
Focus width		2					
Text format							
Table font		Tahoma, 15px		Table header font		Tahoma, 15px, style=Bold	
Toolbar							
"Info text" button		Enabled		Acknowledge button		Enabled	Loop-In-Alarm button Disabled
Toolbar style		Buttons					
Button border							
Width (button border)		1		Style (button border)		Solid	Foreground color (button border) 156, 154, 165
Background color (button border)		156, 154, 165		Corner radius (button border)		3	
Button fill pattern							
Fill pattern (button fill pattern)		Vertical gradient		Background color (button fill pattern)		239, 235, 239	Background color gradient (button fill pattern) 239, 235, 239
Gradient 1 (button fill pattern)		Enabled		Color gradient 1 (button fill pattern)		247, 247, 247	Offset gradient 1 (button fill pattern) 15
Gradient 2 (button fill pattern)		Enabled		Color gradient 2 (button fill pattern)		231, 223, 222	Offset gradient 2 (button fill pattern) 15
Columns							
Columns		Alarm number, Time, Alarm text, Date, Alarm class		Column headers		Enabled	Time in milliseconds Disabled
Time sorting order		Descending					
Column headers							
Alarm number		Default value		Time		Default value	Alarm status Default value
Alarm text		Default value		Alarm class		Default value	Date Default value
Acknowledgment group		Default value		Diagnosable		Default value	PLC (error location) Default value
Table header border							
Width (table header border)		1		Style (table header border)		Solid	Color (table header border) 156, 154, 165
Background color (table header border)		156, 154, 165		Corner radius (table header border)		2	

Totally Integrated Automation Portal		
Table header fill pattern		
Fill pattern (table header fill pattern)	Vertical gradient	Background color gradient (table header fill pattern)239, 235, 239Gradient 1 (table header fill pattern)Enabled
Color gradient 1 (table header fill pattern)	247, 247, 247	Offset gradient 1 (table header fill pattern)15Gradient 2 (table header fill pattern)Enabled
Color gradient 2 (table header fill pattern)	231, 223, 222	Offset gradient 2 (table header fill pattern)15
Styles/Designs		
Use style/design	Disabled	Style item appearance
Miscellaneous		
Name	System events	

Totally Integrated Automation Portal

ChemicalProcess / HMI_1 [KTP700 Basic PN] / HMI tags

Default tag table [17]

Tag_ScreenNumber

General					
Name	Tag_ScreenNumber	Connection	<Internal tag>	Data type	UInt
Array elements	0	Length	2	Address	
Access mode	<symbolic access>	PLC tag		Coding	Binary
PLC name					
Settings					
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation		
Limits					
Upper 2		Lower 2			
Linear scaling					
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0
HMI device value range end value	100	HMI device value range start value	0		
Values					
ID tag		Start value			
Comment					
Comment		Source comment			
Multiplexing					
Multiplexing	Disabled	Index tag			

WT-512

General					
Name	WT-512	Connection	HMI_Connection_1	Data type	Int
Array elements	0	Length	2	Address	
Access mode	<symbolic access>	Coding	Binary	PLC name	PLC_1
Settings					
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation		
Limits					
Upper 2		Lower 2			
Linear scaling					
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0
HMI device value range end value	100	HMI device value range start value	0		
Values					
ID tag		Start value			
Comment					
Comment		Source comment			
Multiplexing					
Multiplexing	Disabled	Index tag			

WT-512

GSV-510

General					
Name	GSV-510	Connection	HMI_Connection_1	Data type	Bool
Array elements	0	Length	1	Address	
Access mode	<symbolic access>	Coding	Binary	PLC name	PLC_1
Settings					
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation		
Limits					
Upper 2		Lower 2			
Linear scaling					
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0
HMI device value range end value	100	HMI device value range start value	0		
Values					
ID tag		Start value			
Comment					
Comment		Source comment			
Multiplexing					
Multiplexing	Disabled	Index tag			

GSV-510

GSV-511

General					
Name	GSV-511	Connection	HMI_Connection_1	Data type	Bool
Array elements	0	Length	1	Address	
Access mode	<symbolic access>	Coding	Binary	PLC name	PLC_1
Settings					
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation		
Limits					
Upper 2		Lower 2			
Linear scaling					
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0

Totally Integrated Automation Portal							
HMI device value range end value		100		HMI device value range start value		0	
Values							
ID tag				Start value			
Comment							
Comment				Source comment			
Multiplexing							
Multiplexing		Disabled		Index tag			
GSV-511							
GSV-514							
General							
Name		GSV-514		Connection		HMI_Connection_1	
Array elements		0		Length		1	
Access mode		<symbolic access>		Coding		Binary	
				PLC name		PLC_1	
Settings							
Acquisition cycle		1 s		Acquisition mode		Cyclic in operation	
Limits							
Upper 2				Lower 2			
Linear scaling							
Linear scaling		Disabled		PLC value range end value		10	
				PLC value range start value		0	
HMI device value range end value		100		HMI device value range start value		0	
Values							
ID tag				Start value			
Comment							
Comment				Source comment			
Multiplexing							
Multiplexing		Disabled		Index tag			
GSV-514							
GSV-519							
General							
Name		GSV-519		Connection		HMI_Connection_1	
Array elements		0		Length		1	
Access mode		<symbolic access>		Coding		Binary	
				PLC name		PLC_1	
Settings							
Acquisition cycle		1 s		Acquisition mode		Cyclic in operation	
Limits							
Upper 2				Lower 2			
Linear scaling							
Linear scaling		Disabled		PLC value range end value		10	
				PLC value range start value		0	
HMI device value range end value		100		HMI device value range start value		0	
Values							
ID tag				Start value			
Comment							
Comment				Source comment			
Multiplexing							
Multiplexing		Disabled		Index tag			
GSV-519							
GSV-521							
General							
Name		GSV-521		Connection		HMI_Connection_1	
Array elements		0		Length		1	
Access mode		<symbolic access>		Coding		Binary	
				PLC name		PLC_1	
Settings							
Acquisition cycle		1 s		Acquisition mode		Cyclic in operation	
Limits							
Upper 2				Lower 2			
Linear scaling							
Linear scaling		Disabled		PLC value range end value		10	
				PLC value range start value		0	
HMI device value range end value		100		HMI device value range start value		0	
Values							
ID tag				Start value			
Comment							
Comment				Source comment			
Multiplexing							
Multiplexing		Disabled		Index tag			
GSV-521							
M001.ST							
General							
Name		M001.ST		Connection		HMI_Connection_1	
Array elements		0		Length		1	
Access mode		<symbolic access>		Coding		Binary	
				PLC name		PLC_1	

Totally Integrated Automation Portal						
Settings						
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation			
Limits						
Upper 2		Lower 2				
Linear scaling						
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0	
HMI device value range end value	100	HMI device value range start value	0			
Values						
ID tag		Start value				
Comment						
Comment		Source comment				
Multiplexing						
Multiplexing	Disabled	Index tag				
M001.ST						
M002.ST						
General						
Name	M002.ST	Connection	HMI_Connection_1	Data type	Bool	
Array elements	0	Length	1	Address		
Access mode	<symbolic access>	Coding	Binary	PLC name	PLC_1	
Settings						
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation			
Limits						
Upper 2		Lower 2				
Linear scaling						
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0	
HMI device value range end value	100	HMI device value range start value	0			
Values						
ID tag		Start value				
Comment						
Comment		Source comment				
Multiplexing						
Multiplexing	Disabled	Index tag				
M002.ST						
M003.ST						
General						
Name	M003.ST	Connection	HMI_Connection_1	Data type	Bool	
Array elements	0	Length	1	Address		
Access mode	<symbolic access>	Coding	Binary	PLC name	PLC_1	
Settings						
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation			
Limits						
Upper 2		Lower 2				
Linear scaling						
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0	
HMI device value range end value	100	HMI device value range start value	0			
Values						
ID tag		Start value				
Comment						
Comment		Source comment				
Multiplexing						
Multiplexing	Disabled	Index tag				
M003.ST						
TT-518						
General						
Name	TT-518	Connection	HMI_Connection_1	Data type	Int	
Array elements	0	Length	2	Address		
Access mode	<symbolic access>	Coding	Binary	PLC name	PLC_1	
Settings						
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation			
Limits						
Upper 2		Lower 2				
Linear scaling						
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0	
HMI device value range end value	100	HMI device value range start value	0			
Values						
ID tag		Start value				
Comment						
Comment		Source comment				
Multiplexing						
Multiplexing	Disabled	Index tag				

Totally Integrated Automation Portal		
--------------------------------------	--	--

TT-518

TT-517

General					
Name	TT-517	Connection	HMI_Connection_1	Data type	Int
Array elements	0	Length	2	Address	
Access mode	<symbolic access>	Coding	Binary	PLC name	PLC_1
Settings					
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation		
Limits					
Upper 2		Lower 2			
Linear scaling					
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0
HMI device value range end value	100	HMI device value range start value	0		
Values					
ID tag		Start value			
Comment					
Comment		Source comment			
Multiplexing					
Multiplexing	Disabled	Index tag			

TT-517

LT-515

General					
Name	LT-515	Connection	HMI_Connection_1	Data type	Int
Array elements	0	Length	2	Address	
Access mode	<symbolic access>	Coding	Binary	PLC name	PLC_1
Settings					
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation		
Limits					
Upper 2		Lower 2			
Linear scaling					
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0
HMI device value range end value	100	HMI device value range start value	0		
Values					
ID tag		Start value			
Comment					
Comment		Source comment			
Multiplexing					
Multiplexing	Disabled	Index tag			

LT-515

LS-513

General					
Name	LS-513	Connection	HMI_Connection_1	Data type	Bool
Array elements	0	Length	1	Address	
Access mode	<symbolic access>	Coding	Binary	PLC name	PLC_1
Settings					
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation		
Limits					
Upper 2		Lower 2			
Linear scaling					
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0
HMI device value range end value	100	HMI device value range start value	0		
Values					
ID tag		Start value			
Comment					
Comment		Source comment			
Multiplexing					
Multiplexing	Disabled	Index tag			

LS-513

M001.R

General					
Name	M001.R	Connection	HMI_Connection_1	Data type	Bool
Array elements	0	Length	1	Address	
Access mode	<symbolic access>	Coding	Binary	PLC name	PLC_1
Settings					
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation		
Limits					
Upper 2		Lower 2			
Linear scaling					
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0
HMI device value range end value	100	HMI device value range start value	0		

--	--	--

Totally Integrated Automation Portal						
Values						
ID tag		Start value				
Comment						
Comment		Source comment				
Multiplexing						
Multiplexing	Disabled	Index tag				
M001.R						
M002.R						
General						
Name	M002.R	Connection	HMI_Connection_1	Data type	Bool	
Array elements	0	Length	1	Address		
Access mode	<symbolic access>	Coding	Binary	PLC name	PLC_1	
Settings						
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation			
Limits						
Upper 2		Lower 2				
Linear scaling						
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0	
HMI device value range end value	100	HMI device value range start value	0			
Values						
ID tag		Start value				
Comment						
Comment		Source comment				
Multiplexing						
Multiplexing	Disabled	Index tag				
M002.R						
M003.R						
General						
Name	M003.R	Connection	HMI_Connection_1	Data type	Bool	
Array elements	0	Length	1	Address		
Access mode	<symbolic access>	Coding	Binary	PLC name	PLC_1	
Settings						
Acquisition cycle	1 s	Acquisition mode	Cyclic in operation			
Limits						
Upper 2		Lower 2				
Linear scaling						
Linear scaling	Disabled	PLC value range end value	10	PLC value range start value	0	
HMI device value range end value	100	HMI device value range start value	0			
Values						
ID tag		Start value				
Comment						
Comment		Source comment				
Multiplexing						
Multiplexing	Disabled	Index tag				
M003.R						

Totally Integrated Automation Portal

ChemicalProcess / HMI_1 [KTP700 Basic PN]

Connections

HMI_Connection_1

Name	HMI_Connection_1	Communication driver	SIMATIC S7 1500	Comment	
Online	Enabled	Station	S71500/ET200MP station_1	Partner	PLC_1
Node	CPU 1511-1 PN, PROFINET interface (R0/S1)	HMI time synchronization mode	None		

Parameter

HMI device					
Interface	PROFINET (X1)	Address	192.168.0.2	Access point	S7ONLINE
PLC					
Address	192.168.0.1				

Totally Integrated Automation Portal		
ChemicalProcess / HMI_1 [KTP700 Basic PN] / HMI alarms Discrete alarms This folder is empty.		

Totally Integrated Automation Portal		
ChemicalProcess / HMI_1 [KTP700 Basic PN] / HMI alarms Analog alarms This folder is empty.		

Totally Integrated Automation Portal		
--------------------------------------	--	--

ChemicalProcess / HMI_1 [KTP700 Basic PN] / HMI alarms

Alarm groups

Alarm_group_1

General			
Name	Alarm_group_1	ID	1

Alarm_group_10

General			
Name	Alarm_group_10	ID	10

Alarm_group_11

General			
Name	Alarm_group_11	ID	11

Alarm_group_12

General			
Name	Alarm_group_12	ID	12

Alarm_group_13

General			
Name	Alarm_group_13	ID	13

Alarm_group_14

General			
Name	Alarm_group_14	ID	14

Alarm_group_15

General			
Name	Alarm_group_15	ID	15

Alarm_group_16

General			
Name	Alarm_group_16	ID	16

Alarm_group_2

General			
Name	Alarm_group_2	ID	2

Alarm_group_3

General			
Name	Alarm_group_3	ID	3

Alarm_group_4

General			
Name	Alarm_group_4	ID	4

Alarm_group_5

General			
Name	Alarm_group_5	ID	5

Alarm_group_6

General			
Name	Alarm_group_6	ID	6

Alarm_group_7

General			
Name	Alarm_group_7	ID	7

Alarm_group_8

General			
Name	Alarm_group_8	ID	8

Alarm_group_9

General			
Name	Alarm_group_9	ID	9

--	--	--

Totally Integrated Automation Portal					
ChemicalProcess / HMI_1 [KTP700 Basic PN] / HMI alarms					
Alarm classes					
Acknowledgement					
General					
Name	Acknowledgement	Display name	A	ID	33
Common alarm class	Acknowledgement	Alarm log	<No log>		
Acknowledgment					
State machine	Alarm with single-mode acknowledgment				
State texts					
Text for "Incoming"	I	Text for "Outgoing"	O	Text for "Acknowledged"	A
Colors					
Background "Incoming/Acknowledged"	255, 255, 255	Background "Incoming"	255, 0, 0	Background "Incoming/Outgoing/Acknowledged"	255, 255, 255
Background "Incoming/Outgoing"	255, 0, 0				
Errors					
General					
Name	Errors	Display name	!	ID	1
Common alarm class	<No alarm class>	Alarm log	<No log>		
Acknowledgment					
State machine	Alarm with single-mode acknowledgment				
State texts					
Text for "Incoming"	I	Text for "Outgoing"	O	Text for "Acknowledged"	A
Colors					
Background "Incoming/Acknowledged"	255, 255, 255	Background "Incoming"	255, 0, 0	Background "Incoming/Outgoing/Acknowledged"	255, 255, 255
Background "Incoming/Outgoing"	255, 0, 0				
No Acknowledgement					
General					
Name	No Acknowledgement	Display name	NA	ID	34
Common alarm class	No Acknowledgement	Alarm log	<No log>		
Acknowledgment					
State machine	Alarm without acknowledgment				
State texts					
Text for "Incoming"	I	Text for "Outgoing"	O	Text for "Acknowledged"	A
Colors					
Background "Incoming/Acknowledged"	255, 255, 255	Background "Incoming"	255, 0, 0	Background "Incoming/Outgoing/Acknowledged"	255, 255, 255
Background "Incoming/Outgoing"	255, 0, 0				
System					
General					
Name	System	Display name	\$	ID	3
Common alarm class	<No alarm class>	Alarm log	<No log>		
Acknowledgment					
State machine	Alarm without acknowledgment				
State texts					
Text for "Incoming"	I	Text for "Outgoing"	O	Text for "Acknowledged"	A
Colors					
Background "Incoming/Acknowledged"	255, 255, 255	Background "Incoming"	255, 255, 255	Background "Incoming/Outgoing/Acknowledged"	255, 255, 255
Background "Incoming/Outgoing"	255, 255, 255				
Warnings					
General					
Name	Warnings	Display name		ID	2
Common alarm class	<No alarm class>	Alarm log	<No log>		
Acknowledgment					
State machine	Alarm without acknowledgment				
State texts					
Text for "Incoming"	I	Text for "Outgoing"	O	Text for "Acknowledged"	A
Colors					
Background "Incoming/Acknowledged"	255, 255, 255	Background "Incoming"	255, 255, 255	Background "Incoming/Outgoing/Acknowledged"	255, 255, 255

Totally Integrated Automation Portal		
Background "Incoming/Outgoing"	255, 255, 255	

Totally Integrated Automation Portal		
ChemicalProcess / HMI_1 [KTP700 Basic PN] / HMI alarms System events This folder is empty.		

Totally Integrated Automation Portal		
ChemicalProcess / HMI_1 [KTP700 Basic PN] Recipes This folder is empty.		

Totally Integrated Automation Portal		
ChemicalProcess / HMI_1 [KTP700 Basic PN] / Historical data Datalogs This folder is empty.		

Totally Integrated Automation Portal		
ChemicalProcess / HMI_1 [KTP700 Basic PN] / Historical data AlarmLogs This folder is empty.		

Totally Integrated Automation Portal		
ChemicalProcess / HMI_1 [KTP700 Basic PN] Scheduled tasks This folder is empty.		

Totally Integrated Automation Portal

ChemicalProcess / HMI_1 [KTP700 Basic PN] / Text and graphic lists

Text lists

TextList_OriginalScreenNames

Name	TextList_OriginalScreenNames	List range	Value/Range	Comment	
Value: 1					
Entry type	Single value		Text	Root screen	
Value: 2					
Entry type	Single value		Text	System screens	
Value: 3					
Entry type	Single value		Text	SIMATIC PLC system diagnostics	
Value: 4					
Entry type	Single value		Text	Project information	
Value: 5					
Entry type	Single value		Text	User administration	
Value: 6					
Entry type	Single value		Text	System information	
Value: 7					
Entry type	Single value		Text	Different jobs	

TextList_ScreenNames

Name	TextList_ScreenNames	List range	Value/Range	Comment	
Value: 1					
Entry type	Single value		Text	Root screen	
Value: 2					
Entry type	Single value		Text	System screens	
Value: 3					
Entry type	Single value		Text	SIMATIC PLC system diagnostics	
Value: 4					
Entry type	Single value		Text	Project information	
Value: 5					
Entry type	Single value		Text	User administration	
Value: 6					
Entry type	Single value		Text	System information	
Value: 7					
Entry type	Single value		Text	Different jobs	

Totally Integrated Automation Portal		
ChemicalProcess / HMI_1 [KTP700 Basic PN] / Text and graphic lists Graphic lists This folder is empty.		

Totally Integrated Automation Portal		
--------------------------------------	--	--

ChemicalProcess / HMI_1 [KTP700 Basic PN] / User administration

User

Administrator

General			
Name	Administrator	Number	1
Automatic logoff			
Automatic logoff	Enabled	Logoff time	5
Comment			
Comment	The user 'Administrator' is assigned to the 'Administrator' group.		
Groups			
Groups	Administrator group;		

--	--	--

Totally Integrated Automation Portal

ChemicalProcess / HMI_1 [KTP700 Basic PN] / User administration

Groups

Administrator group

General

Name

Administrator group

Display name

Administrator group

Number

1

Password aging

Disabled

Comment

The 'Administrator' group is initially granted all rights.

Authorizations

User administration; Monitor; Operate;

Users

General

Name

Users

Display name

Users

Number

2

Password aging

Disabled

Comment

The 'Users' group is initially granted 'Operating' rights.

Authorizations

Operate;

Totally Integrated Automation Portal		
--------------------------------------	--	--

ChemicalProcess / HMI_1 [KTP700 Basic PN] / User administration

Authorizations

Monitor

General					
Name	Monitor	Authorization	Monitor	Authorization number	2
Comment					
Comment	'Monitor' authorization.				

Operate

General					
Name	Operate	Authorization	Operate	Authorization number	3
Comment					
Comment	'Operate' authorization.				

User administration

General					
Name	User administration	Authorization	User administration	Authorization number	1
Comment					
Comment	Authorization 'User administration' for managing users in the user view in Runtime.				

--	--	--

Totally Integrated Automation Portal		
ChemicalProcess Ungrouped devices This folder is empty.		

Totally Integrated Automation Portal		
ChemicalProcess Security settings This folder is empty.		

Totally Integrated Automation Portal		
ChemicalProcess / Cross-device functions / Project traces Measurements This folder is empty.		

Totally Integrated Automation Portal		
--------------------------------------	--	--

ChemicalProcess / Common data

Alarm classes

Alarm classes			
Name	Display name	Acknowledgment	Priority
Acknowledgement	A	True	0
No Acknowledgement	NA	False	0

--	--	--

Totally Integrated Automation Portal		
ChemicalProcess / Common data Logs This folder is empty.		

Totally Integrated Automation Portal		
ChemicalProcess / Common data Styles This folder is empty.		

Totally Integrated Automation Portal		
ChemicalProcess / Languages & resources Project languages Languages Reference language English (United States) Editing language English (United States) Other project languages Empty		

Totally Integrated Automation Portal																																																																																																																																																																																						
ChemicalProcess / Languages & resources / Project texts Project texts <table><tr><th colspan="3">Project texts</th></tr><tr><th>English (United States)</th><th>Category</th><th>Reference</th></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 1\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 2\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 3\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 4\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 5\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 6\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 7\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 8\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 9\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 10\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 11\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 12\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 13\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 14\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 15\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 16\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 1\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 2\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 3\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 4\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 5\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 6\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 7\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 8\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 9\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 10\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 11\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 12\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 13\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 14\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 15\Description</td></tr><tr><td></td><td>Multilingual text category</td><td>Subcategory 16\Description</td></tr><tr><td></td><td>Block comment</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Sequence \Step\Actions\Comment</td></tr><tr><td></td><td>Block comment</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 8\Comment</td></tr><tr><td></td><td>Alarm class text</td><td>ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Errors\alarmclass name not set\Short-Name</td></tr><tr><td></td><td>Alarm class text</td><td>ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Warnings\alarmclass name not set_1\ShortName</td></tr><tr><td></td><td>Alarm class text</td><td>ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\System\alarmclass name not set_2\ShortName</td></tr><tr><td></td><td>Alarm class text</td><td>ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Diagnosis events\alarmclass name not set_3\ShortName</td></tr><tr><td></td><td>Alarm class text</td><td>ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Safety warnings\alarmclass name not set_4\ShortName</td></tr><tr><td></td><td>Alarm class text</td><td>ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Acknowledgement\\ShortName</td></tr><tr><td></td><td>Alarm class text</td><td>ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\No Acknowledgement\\ShortName</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 1\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 1\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 2\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 2\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 3\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 3\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 4\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 4\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 5\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 5\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 6\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 6\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 7\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 7\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 8\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 8\Text</td></tr><tr><td></td><td>Text List Text Category</td><td>ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 9\Text</td></tr></table>	Project texts			English (United States)	Category	Reference		Multilingual text category	Subcategory 1\Description		Multilingual text category	Subcategory 2\Description		Multilingual text category	Subcategory 3\Description		Multilingual text category	Subcategory 4\Description		Multilingual text category	Subcategory 5\Description		Multilingual text category	Subcategory 6\Description		Multilingual text category	Subcategory 7\Description		Multilingual text category	Subcategory 8\Description		Multilingual text category	Subcategory 9\Description		Multilingual text category	Subcategory 10\Description		Multilingual text category	Subcategory 11\Description		Multilingual text category	Subcategory 12\Description		Multilingual text category	Subcategory 13\Description		Multilingual text category	Subcategory 14\Description		Multilingual text category	Subcategory 15\Description		Multilingual text category	Subcategory 16\Description		Multilingual text category	Subcategory 1\Description		Multilingual text category	Subcategory 2\Description		Multilingual text category	Subcategory 3\Description		Multilingual text category	Subcategory 4\Description		Multilingual text category	Subcategory 5\Description		Multilingual text category	Subcategory 6\Description		Multilingual text category	Subcategory 7\Description		Multilingual text category	Subcategory 8\Description		Multilingual text category	Subcategory 9\Description		Multilingual text category	Subcategory 10\Description		Multilingual text category	Subcategory 11\Description		Multilingual text category	Subcategory 12\Description		Multilingual text category	Subcategory 13\Description		Multilingual text category	Subcategory 14\Description		Multilingual text category	Subcategory 15\Description		Multilingual text category	Subcategory 16\Description		Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Sequence \Step\Actions\Comment		Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 8\Comment		Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Errors\alarmclass name not set\Short-Name		Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Warnings\alarmclass name not set_1\ShortName		Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\System\alarmclass name not set_2\ShortName		Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Diagnosis events\alarmclass name not set_3\ShortName		Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Safety warnings\alarmclass name not set_4\ShortName		Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Acknowledgement\\ShortName		Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\No Acknowledgement\\ShortName		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 1\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 1\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 2\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 2\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 3\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 3\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 4\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 4\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 5\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 5\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 6\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 6\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 7\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 7\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 8\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 8\Text		Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 9\Text		
Project texts																																																																																																																																																																																						
English (United States)	Category	Reference																																																																																																																																																																																				
	Multilingual text category	Subcategory 1\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 2\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 3\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 4\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 5\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 6\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 7\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 8\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 9\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 10\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 11\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 12\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 13\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 14\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 15\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 16\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 1\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 2\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 3\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 4\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 5\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 6\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 7\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 8\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 9\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 10\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 11\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 12\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 13\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 14\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 15\Description																																																																																																																																																																																				
	Multilingual text category	Subcategory 16\Description																																																																																																																																																																																				
	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Sequence \Step\Actions\Comment																																																																																																																																																																																				
	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 8\Comment																																																																																																																																																																																				
	Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Errors\alarmclass name not set\Short-Name																																																																																																																																																																																				
	Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Warnings\alarmclass name not set_1\ShortName																																																																																																																																																																																				
	Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\System\alarmclass name not set_2\ShortName																																																																																																																																																																																				
	Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Diagnosis events\alarmclass name not set_3\ShortName																																																																																																																																																																																				
	Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Safety warnings\alarmclass name not set_4\ShortName																																																																																																																																																																																				
	Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Acknowledgement\\ShortName																																																																																																																																																																																				
	Alarm class text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\No Acknowledgement\\ShortName																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 1\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 1\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 2\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 2\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 3\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 3\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 4\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 4\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 5\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 5\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 6\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 6\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 7\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 7\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 8\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_InterlockAlarm-Texts639139229410127278_1\Range 8\Text																																																																																																																																																																																				
	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_SupervisionAlarm-Texts639139229410057278_1\Range 9\Text																																																																																																																																																																																				

Totally Integrated Automation Portal		
English (United States)	Category	Reference
	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Tem-plate_Button_1\Text OFF
	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Tem-plate_Button_1\Text ON
	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Tem-plate_Button_2\Text OFF
	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Tem-plate_Button_2\Text ON
	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Tem-plate_Button_3\Text OFF
	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Tem-plate_Button_3\Text ON
	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_3\Text
	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_5\Text
--	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 0\Text
--	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 0\Text
!	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Errors\alarmclass name not set\Alarm-ClassData_IDisplayNaming_DisplayName
!!	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Safety warnings\alarmclass name not set_4\AlarmClassData_IDisplayNaming_DisplayName
"Main Program Sweep (Cycle)"	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Block title
\$	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\System\alarmclass name not set_2\AlarmClassData_IDisplayNaming_DisplayName
(not configured)	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Project information\HmiScreenItemDa-ta_7\Text
@2%t#SYSTEM_Global_ProDiag_Supervision-Categories@ : @2%t#SYSTEM_Global_Pro-Diag_SupervisionTypes@ : \$\$CpuName\$\$: ProcessSequence : @1%t#SYSTEM_Step-Names639139229409982114_1@ : S@1%03d@ : @1%t#SYSTEM_InterlockAlarm-Texts639139229410127278_1@	Formatted alarm text	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence_DB [DB3]\IL_ALARM_INST\Alarm text
@2%t#SYSTEM_Global_ProDiag_Supervision-Categories@ : @2%t#SYSTEM_Global_Pro-Diag_SupervisionTypes@ : \$\$CpuName\$\$: ProcessSequence : @1%t#SYSTEM_Step-Names639139229409982114_1@ : S@1%03d@ : @1%t#SYSTEM_SupervisionA-larmTexts639139229410057278_1@	Formatted alarm text	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence_DB [DB3]\SUP_ALARM_INST\Alarm text
@2%t#SYSTEM_Global_ProDiag_Supervision-Categories@ : @2%t#SYSTEM_Global_Pro-Diag_SupervisionTypes@ : \$\$CpuName\$\$: ProcessSequence : @1%t#SYSTEM_Step-Names639139229409982114_1@ : S@1%03d@ : @1%t#SYSTEM_SupervisionA-larmTexts639139229410057278_1@	Formatted alarm text	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence_DB [DB3]\STEP_TIME_ALARM_INST\Alarm text
Project information	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System screens\HmiScreenItemDa-ta_1\Text OFF
Project information	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System screens\HmiScreenItemDa-ta_1\Text ON
SIMATIC PLC system diagnos...	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System screens\HmiScreenItemData\Text OFF
SIMATIC PLC system diagnos...	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System screens\HmiScreenItemData\Text ON
System information	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System screens\HmiScreenItemDa-ta_3\Text OFF
System information	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System screens\HmiScreenItemDa-ta_3\Text ON
User administration	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System screens\HmiScreenItemDa-ta_2\Text OFF
User administration	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System screens\HmiScreenItemDa-ta_2\Text ON
0	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Sym-bolic_IO_Field_Screen\Text OFF
1	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Sym-bolic_IO_Field_Screen\Text ON
1200-1800KG in wight sensor = 600Kg of Powder	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Sequence \Step\Actions\Comment
1Litre = 1Kg, 0-600Kg in Weight sensor is 600litres of Water For forcing value of sensors converts kg value to Siemens analog raw value (0...27648). For 200KG = 2765	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Sequence \Step\Actions\Comment
5/25/2021 10:32:50 AM	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Project information\HmiScreenItemDa-ta_3\Text
600Kg to 1200kg in weight sensor is 600Kg of NaOH.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Sequence \Step\Actions\Comment
A	Alarm class text	ChemicalProcess\Acknowledgement\AlarmClassData_IDisplayNaming_DisplayName
A	Alarm class text	ChemicalProcess\Acknowledgement\ShortName
A	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Errors\AcknowledgedText
A	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Warnings\AcknowledgedText
A	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\System\AcknowledgedText
A	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Diagnosis events\AcknowledgedText
A	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Safety warnings\AcknowledgedText
A	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Acknowledgement\AcknowledgedText
A	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\No Acknowledgement\Acknowledged-Text
Acknowledge all errors and faults	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\ACK_EF
Action	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 104\Text
Action	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 204\Text
Action	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 304\Text
Action	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 404\Text

Totally Integrated Automation Portal		
English (United States)	Category	Reference
Action	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 504\Text
Action	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 604\Text
Action	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 704\Text
Action	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 804\Text
Activates remote authorization for the use of client-server scenarios.	HMI comment	ChemicalProcess\HMI_1 [KTP700 Basic PN]\User administration\Enable remote controll\Comment
Active system events	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Global screen\System events\Label
Administrator group	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\User administration\Administrator group\Display-Name
Alarms	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Alarms\Text OFF
Alarms	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Alarms\Text ON
Author:	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Project information\HmiScreenItemData_4\Text
Authorization 'User administration' for managing users in the user view in Runtime.	HMI comment	ChemicalProcess\HMI_1 [KTP700 Basic PN]\User administration\User administration\Comment
Automode	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 2\Title
Automode makes sytem run automatically until pressed stop.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Auto
Back	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System screens\Back\Text OFF
Back	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System screens\Back\Text ON
Back	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\SIMATIC PLC system diagnostics\Back\Text OFF
Back	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\SIMATIC PLC system diagnostics\Back\Text ON
Back	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Project information\Back\Text OFF
Back	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Project information\Back\Text ON
Back	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\User administration\Back\Text OFF
Back	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\User administration\Back\Text ON
Back	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System information\Back\Text OFF
Back	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System information\Back\Text ON
Back	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Different jobs\Back\Text OFF
Back	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Different jobs\Back\Text ON
Basci scale block	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\FC_Scale [FC2]\Network 1\Comment
Basic FC to FB call.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\SensorScaling [FB3]\Network 1\Comment
Calls motor FB instances and maps sequence/manual commands to physical motor outputs.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 10\Comment
Calls valve FB instances and maps sequence/manual commands to physical valve outputs.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 9\Comment
Category : Supervision type : PLC name : FB name : Step name : Step number : Step specific field	Formatted alarm text	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\IL_ALARM_INST\Alarm text
Category : Supervision type : PLC name : FB name : Step name : Step number : Step specific field	Formatted alarm text	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\SUP_ALARM_INST\Alarm text
Category : Supervision type : PLC name : FB name : Step name : Step number : Step specific field	Formatted alarm text	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\STEP_TIME_ALARM_INST\Alarm text
Category 4	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 401\Text
Category 4	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 402\Text
Category 4	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 403\Text
Category 4	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 404\Text
Category 4	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 405\Text
Category 4	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 406\Text
Category 4	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 407\Text
Category 4	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 408\Text
Category 4	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 409\Text
Category 4	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 410\Text
Category 5	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 501\Text
Category 5	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 502\Text
Category 5	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 503\Text
Category 5	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 504\Text
Category 5	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 505\Text
Category 5	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 506\Text
Category 5	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 507\Text
Category 5	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 508\Text
Category 5	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 509\Text
Category 5	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 510\Text
Category 6	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 601\Text
Category 6	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 602\Text
Category 6	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 603\Text
Category 6	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 604\Text
Category 6	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 605\Text
Category 6	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 606\Text
Category 6	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 607\Text
Category 6	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 608\Text
Category 6	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 609\Text
Category 6	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 610\Text
Category 7	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 701\Text
Category 7	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 702\Text
Category 7	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 703\Text
Category 7	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 704\Text
Category 7	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 705\Text
Category 7	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 706\Text

Totally Integrated Automation Portal		
English (United States)	Category	Reference
Category 7	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 707\Text
Category 7	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 708\Text
Category 7	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 709\Text
Category 7	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 710\Text
Category 8	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 801\Text
Category 8	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 802\Text
Category 8	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 803\Text
Category 8	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 804\Text
Category 8	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 805\Text
Category 8	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 806\Text
Category 8	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 807\Text
Category 8	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 808\Text
Category 8	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 809\Text
Category 8	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 810\Text
ChemicalProcess	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Project information\HmiScreenItemData_1\Text
Close NaOH valve	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step-Names639139229409982114_1\Range 7\Text
Collects process, device, sensor, and emergency stop faults into one fault status.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 5\Comment
Connect the sensor Straight here. 4-20mA = 0-27648 Integers.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\FC_Scale [FC2]\RawValue
Connect the sensor Straight here. 4-20mA = 0-27648 Integers.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\SensorScaling [FB3]\RawValue
Connection:	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System information\HmiScreenItemData_2\Text
Created on:	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Project information\HmiScreenItemData_2\Text
Creates automatic operation enable signal from HMI mode selection and start/stop commands.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 2\Comment
Creates global all outputs ON/OFF test commands.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 6\Comment
Creates manual operation enable signal for direct operator-controlled device operation.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 3\Comment
Current sensor for PumpM003	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Scaled_FIC516
Description:	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Project information\HmiScreenItemData_6\Text
Different jobs	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Text and graphic lists\TextList_ScreenNames\Text_list_entry_7\Text
Different jobs	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Text and graphic lists\TextList_OriginalScreenNames\Text_list_entry_7\Text
Different jobs	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System screens\HmiScreenItemData_4\Text OFF
Different jobs	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System screens\HmiScreenItemData_4\Text ON
Elaspse time for mix tank motor	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\SetElapseTimeforMixing
Emergency Stop	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 4\Title
Empty MIX Tank	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step-Names639139229409982114_1\Range 5\Text
Empty Storage Tank	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step-Names639139229409982114_1\Range 10\Text
Error	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 101\Text
Error	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 102\Text
Error	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 103\Text
Error	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 104\Text
Error	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 105\Text
Error	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 106\Text
Error	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 107\Text
Error	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 108\Text
Error	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 109\Text
Error	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 110\Text
Error message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 106\Text
Error message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 206\Text
Error message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 306\Text
Error message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 406\Text
Error message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 506\Text
Error message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 606\Text
Error message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 706\Text
Error message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 806\Text
Exit	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Exit\Text OFF
Exit	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Exit\Text ON
Exit valve close	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step-Names639139229409982114_1\Range 15\Text
Exit valve open	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step-Names639139229409982114_1\Range 12\Text
Fault	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 5\Title
FIC-516 is Pressure sensor Integrated with M003	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\FIC_516
Fill NaOH	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step-Names639139229409982114_1\Range 2\Text
Fill Powder M001	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step-Names639139229409982114_1\Range 3\Text
Fill water	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step-Names639139229409982114_1\Range 17\Text



















Totally Integrated Automation Portal		
English (United States)	Category	Reference
GRAPH-Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 108\Text
GRAPH-Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 208\Text
GRAPH-Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 308\Text
GRAPH-Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 408\Text
GRAPH-Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 508\Text
GRAPH-Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 608\Text
GRAPH-Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 708\Text
GRAPH-Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 808\Text
GRAPH-Supervision	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 109\Text
GRAPH-Supervision	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 209\Text
GRAPH-Supervision	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 309\Text
GRAPH-Supervision	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 409\Text
GRAPH-Supervision	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 509\Text
GRAPH-Supervision	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 609\Text
GRAPH-Supervision	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 709\Text
GRAPH-Supervision	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 809\Text
GRAPH-Warning	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 110\Text
GRAPH-Warning	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 210\Text
GRAPH-Warning	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 310\Text
GRAPH-Warning	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 410\Text
GRAPH-Warning	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 510\Text
GRAPH-Warning	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 610\Text
GRAPH-Warning	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 710\Text
GRAPH-Warning	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 810\Text
GSV_510 Valve	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\GSV_510
GSV-510	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_2\Text
GSV-511	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_4\Text
GSV-511 Valve	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\GSV_511
GSV-514	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_6\Text
GSV-519	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_7\Text
GSV-521	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_8\Text
High limit required in plan	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\FC_Scale [FC2]\HighLimitForSensor
High limit required in plan	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\SensorScaling [FB3]\HighLimitForSensor
HMI	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 1\Title
HMI device type:	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System information\HmiScreen\ItemData \Text
I	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Errors\ComingText
I	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Warnings\ComingText
I	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\System\ComingText
I	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Diagnosis events\ComingText
I	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Safety warnings\ComingText
I	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Acknowledgement\ComingText
I	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\No Acknowledgement\ComingText
If limit is negative then Bipolar:= true elseif positive then unipolar:= true	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\FC_Scale [FC2]\DoLimitIsNegative
If limit is negative then Bipolar:= true elseif positive then unipolar:= true	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\SensorScaling [FB3]\DoLimitIsNegative
If Valve opens have to make sure it closes.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Sequence \Step\Actions\Comment
Info	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 301\Text
Info	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 302\Text
Info	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 303\Text
Info	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 304\Text
Info	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 305\Text
Info	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 306\Text
Info	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 307\Text
Info	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 308\Text
Info	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 309\Text
Info	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionCategories\Range 310\Text
Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 102\Text
Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 202\Text
Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 302\Text
Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 402\Text
Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 502\Text
Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 602\Text
Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 702\Text
Interlock	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 802\Text
Internal data area	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\RT_DATA
IO	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Errors\ComingGoingText
IO	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Warnings\ComingGoingText
IO	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\System\ComingGoingText
IO	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Diagnosis events\ComingGoingText
IO	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Safety warnings\ComingGoingText
IO	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Acknowledgement\ComingGoingText
IO	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\No Acknowledgement\ComingGoing-Text
KTP700 Basic+ PN 16.0.0.0	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System information\HmiScreen\ItemDa-ta_1\Text
Language	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Language\Text OFF
Language	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Language\Text ON
Low limit required in plan	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\FC_Scale [FC2]\LowLimitForSensor



Totally Integrated Automation Portal		
English (United States)	Category	Reference
Low limit required in plan	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\SensorScaling [FB3]\LowLimitForSensor
LS-513 Powder Low level Button	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\LSA_513
LT/LI-515 sensor´s scaled value	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Scaled_LI515
LT-515	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_12\Text
LT-515 Level indicative sensor	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\LI_515
M001	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_9\Text
M001.F fault signal of Powder Motor	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\M001_F
M001.ST is Powder Motor start signal.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\M001_ST
M001.TK is Temperature protection of POWder Motor.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\M001_TK
M002	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_11\Text
M002.ST is Mixtank Motor signal.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\M002_ST
M003	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_10\Text
M003.F is Fault signal of Motor M003	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\M003_F
M003.R is Reset signal of Motor M003	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\M003_R
M003.ST is Start signal of Motor M003	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\M003_ST
M003.TK isTemperature protection signal of Motor M003	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\M003_TK
Manual mode make user start everytime time the storage tank is emptied.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Manual
ManualMode	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 3\Title
Mator Fault signal For Mix Tank motor	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\M002_F
mika3	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Project information\HmiScreen\ItemData_5\Text
Mlx Tank Motor timing	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\SetTimeForMixing
Monitor	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\User administration\Monitor\ShortName
'Monitor' authorization.	HMI comment	ChemicalProcess\HMI_1 [KTP700 Basic PN]\User administration\Monitor\Comment
Motors	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 10\Title
NA	Alarm class text	ChemicalProcess\No Acknowledgement\AlarmClassData_IDisplayNaming_DisplayName
NA	Alarm class text	ChemicalProcess\No Acknowledgement\ShortName
Not in use for now. Reads operator commands and prepares start, stop, reset, auto/manual selections.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 1\Comment
Not to Storage	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step-Names639139229409982114_1\Range 14\Text
O	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Errors\GoingText
O	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Warnings\GoingText
O	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\System\GoingText
O	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Diagnosis events\GoingText
O	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Safety warnings\GoingText
O	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Acknowledgement\GoingText
O	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\No Acknowledgement\GoingText
OFF	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_1\Text OFF
OFF	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_2\Text OFF
OFF	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_3\Text OFF
OFF	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_4\Text OFF
OFF	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_5\Text OFF
OFF	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_6\Text OFF
OFF	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_7\Text OFF
OFF	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_8\Text OFF
Offline	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Different jobs\Offline\Text OFF
Offline	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Different jobs\Offline\Text ON
ON	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_1\Text ON
ON	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_2\Text ON
ON	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_3\Text ON
ON	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_4\Text ON
ON	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_5\Text ON
ON	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_6\Text ON
ON	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_7\Text ON
ON	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_8\Text ON
Online	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Different jobs\Online\Text OFF
Online	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Different jobs\Online\Text ON
Operand	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 101\Text
Operand	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 201\Text
Operand	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 301\Text
Operand	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 401\Text
Operand	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 501\Text
Operand	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 601\Text
Operand	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 701\Text
Operand	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 801\Text
Operate	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\User administration\Operate\ShortName
'Operate' authorization.	HMI comment	ChemicalProcess\HMI_1 [KTP700 Basic PN]\User administration\Operate\Comment
Pending alarms	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Global screen\Alarm window_Pending\Label
PID FIC-516 /M003	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 8\Title
PIDTulo	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\M003_SP
PLC:	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System information\HmiScreen\ItemData_4\Text
Position	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 105\Text
Position	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 205\Text
Position	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 305\Text
Position	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 405\Text
Position	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 505\Text
Position	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 605\Text

Totally Integrated Automation Portal		
English (United States)	Category	Reference
Position	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 705\Text
Position	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 805\Text
Powder Motor Stop	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step-Names639139229409982114_1\Range 8\Text
Process Sequence	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 11\Title
Processes emergency stop input and creates global emergency stop active signal.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 4\Comment
PROFINET (X1)	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System information\HmiScreenItemData_3\Text
Project information	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Text and graphic lists\TextList_ScreenNames\Text_list_entry_4\Text
Project information	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Text and graphic lists\TextList_OriginalScreenNames\Text_list_entry_4\Text
Project name:	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Project information\HmiScreenItemData\Text
QGR	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Runtime settings\HmiAlarmSettingsData\AcknowledgementGroupText
Reaction	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 103\Text
Reaction	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 203\Text
Reaction	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 303\Text
Reaction	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 403\Text
Reaction	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 503\Text
Reaction	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 603\Text
Reaction	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 703\Text
Reaction	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 803\Text
Reserved for future PID, VFD, alarms, diagnostics, or reporting logic.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 12\Comment
Reset for Mixing Motor	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\M002_R
Reset of Powder Motor	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\M001_R
Reset output	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Motors\Generic Motors\FC_Motor_Reset [FC6]\Network 1\Title
Reset signal to motor memory	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Motors\Generic Motors\FC_Motor_Reset [FC6]\bReset_QFC
Reset signal to valve memory	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Valves\Generic valves\Valves [FC1]\bReset_QFC
Reset valve close command	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Valves\Generic valves\Valves [FC1]\bReset_IFC
Root screen	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Text and graphic lists\TextList_ScreenNames\Text_list_entry_1\Text
Root screen	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Text and graphic lists\TextList_OriginalScreenNames\Text_list_entry_1\Text
Runs GRAPH process sequence for automatic batch operation.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 11\Comment
S7	Alarm text	ChemicalProcess\HMI_1 [KTP700 Basic PN]\HMI alarms\Diagnosis events\alarmclass name not set_3\AlarmClassData_IDisplayNaming_DisplayName
Scales raw analog sensor values into engineering units for process logic.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 7\Comment
Scaling for Sensors	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\FC_Scale [FC2]\Block title
Sensor Fb Block	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\SensorScaling [FB3]\Block title
Sensors Scalings	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 7\Title
Set signal to motor memory	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Motors\Generic Motors\FC_Motor_Set [FC5]\Network 1\Title
Set signal to motor memory	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Motors\Generic Motors\FC_Motor_Set [FC5]\bSet_QFC
Set signal to valve memory	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Valves\Generic valves\Valves [FC1]\Network 1\Title
Set signal to valve memory	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Valves\Generic valves\Valves [FC1]\bSet_QFC
Set valve open command	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Valves\Generic valves\Valves [FC1]\bSet_IFC
SIMATIC PLC system diagnostics	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Text and graphic lists\TextList_ScreenNames\Text_list_entry_3\Text
SIMATIC PLC system diagnostics	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Text and graphic lists\TextList_OriginalScreenNames\Text_list_entry_3\Text
SIMATIC S7 1500	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\System information\HmiScreenItemData_5\Text
Spare/Future Expansion	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 12\Title
Start	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step-Names639139229409982114_1\Range 1\Text
Start initiates the program	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Initiate
Start Mixing	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step-Names639139229409982114_1\Range 4\Text
Start request for motor	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Motors\Generic Motors\FC_Motor_Set [FC5]\bStart_IFC
Start screen	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Start screen\Text OFF
Start screen	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Templates\Template_1\Start screen\Text ON
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Powder Motor Stop
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Fill Powder M001
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Start Mixing
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Empty MIX Tank
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Fill water
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Stop Water

Totally Integrated Automation Portal		
English (United States)	Category	Reference
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Close NaOH valve
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Fill NaOH
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Stop Mixing
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Empty Stor- age Tank
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Stop empty- ing
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Step18
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Start
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Exit valve open
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Valve 521 Stays open
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Exit valve close
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Not to Stor- age
Step structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Step13
Step13	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step- Names639139229409982114_1\Range 13\Text
Step18	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step- Names639139229409982114_1\Range 18\Text
Stop emptying	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step- Names639139229409982114_1\Range 11\Text
Stop Emptying	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Sequence \Step\Interlock\Title
Stop Mixing	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step- Names639139229409982114_1\Range 9\Text
Stop request for motor	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Motors\Generic Motors\FC_Mo- tor_Reset [FC6]\bStop_IFC
Stop Runtime	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Different jobs\Stop Runtime\Text OFF
Stop Runtime	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Different jobs\Stop Runtime\Text ON
Stop the Process and goest back S and wait un- til pressed start manually	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\StopandWait
Stop Water	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Step- Names639139229409982114_1\Range 6\Text
Subcategory 1	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 1\Text
Subcategory 1	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 1\Text
Subcategory 10	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 10\Text
Subcategory 10	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 10\Text
Subcategory 11	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 11\Text
Subcategory 11	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 11\Text
Subcategory 12	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 12\Text
Subcategory 12	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 12\Text
Subcategory 13	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 13\Text
Subcategory 13	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 13\Text
Subcategory 14	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 14\Text
Subcategory 14	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 14\Text
Subcategory 15	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 15\Text
Subcategory 15	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 15\Text
Subcategory 16	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 16\Text
Subcategory 16	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 16\Text
Subcategory 2	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 2\Text
Subcategory 2	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 2\Text
Subcategory 3	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 3\Text
Subcategory 3	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 3\Text
Subcategory 4	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 4\Text
Subcategory 4	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 4\Text
Subcategory 5	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 5\Text
Subcategory 5	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 5\Text
Subcategory 6	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 6\Text
Subcategory 6	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 6\Text
Subcategory 7	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 7\Text
Subcategory 7	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 7\Text
Subcategory 8	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 8\Text
Subcategory 8	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 8\Text
Subcategory 9	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories1\Range 9\Text
Subcategory 9	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionSubCategories2\Range 9\Text
Switch	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_1\Caption text
Switch	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_2\Caption text
Switch	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_3\Caption text
Switch	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_4\Caption text
Switch	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_5\Caption text
Switch	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_6\Caption text
Switch	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_7\Caption text
Switch	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Switch_8\Caption text
System information	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Text and graphic lists\TextList_ScreenNames \Text_list_entry_6\Text
System information	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Text and graphic lists\TextList_OriginalScreen- Names\Text_list_entry_6\Text
System screens	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Text and graphic lists\TextList_ScreenNames \Text_list_entry_2\Text
System screens	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Text and graphic lists\TextList_OriginalScreen- Names\Text_list_entry_2\Text
System screens	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\HmiScreenItemData_1\Text OFF

Totally Integrated Automation Portal		
English (United States)	Category	Reference
System screens	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\HmiScreen\ItemData_1\Text ON
Test mode enable	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\FB_TestMode [FB9]\TestOn
TestMode	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Network 6\Title
Text message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 107\Text
Text message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 207\Text
Text message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 307\Text
Text message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 407\Text
Text message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 507\Text
Text message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 607\Text
Text message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 707\Text
Text message	Text List Text Category	ChemicalProcess\SYSTEM_Global_ProDiag_SupervisionTypes\Range 807\Text
The 'Administrator' group is initially granted all rights.	HMI comment	ChemicalProcess\HMI_1 [KTP700 Basic PN]\User administration\Administrator group\Comment
The idea is to call this from FC and then call it into OB and connect sensors individually, by doing that DB instance can be created for sensors and everythin will be connected inside one and highest layer, this will help in maintenance, monitoring, optimization, further analysis and future possibilities.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\SensorScaling [FB3]\Block comment
The user 'Administrator' is assigned to the 'Administrator' group.	HMI comment	ChemicalProcess\HMI_1 [KTP700 Basic PN]\User administration\Administrator\Comment
The 'Users' group is initially granted 'Operating' rights.	HMI comment	ChemicalProcess\HMI_1 [KTP700 Basic PN]\User administration\Users\Comment
This is a basic mechanism for scaling Sensors. For details about using Function scale, visit this website https://support.industry.siemens.com/cs/document/1765297/how-and-for-which-analog-measurements-can-you-use-the-function-fc105-scale-to-convert-the-integer-values-(int)-into-real-number-values?dti=0&lc=en-SZ	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\FC_Scale [FC2]\Block comment
This is where physical world meets the digital world. Main cyclic control block. Calls HMI handling, operating modes, safety/fault logic, sensor scaling, actuator control, and process sequence in defined order.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Block comment
Toggle language	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Different jobs\Toggle language\Text OFF
Toggle language	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Different jobs\Toggle language\Text ON
Trans1	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Transition-Names639139229410197280_1\Range 1\Text
Trans10	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Transition-Names639139229410197280_1\Range 10\Text
Trans11	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Transition-Names639139229410197280_1\Range 11\Text
Trans12	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Transition-Names639139229410197280_1\Range 12\Text
Trans2	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Transition-Names639139229410197280_1\Range 2\Text
Trans3	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Transition-Names639139229410197280_1\Range 3\Text
Trans4	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Transition-Names639139229410197280_1\Range 4\Text
Trans5	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Transition-Names639139229410197280_1\Range 5\Text
Trans6	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Transition-Names639139229410197280_1\Range 6\Text
Trans7	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Transition-Names639139229410197280_1\Range 7\Text
Trans8	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Transition-Names639139229410197280_1\Range 8\Text
Trans9	Text List Text Category	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\PLC_1\SYSTEM_Transition-Names639139229410197280_1\Range 9\Text
Transfer	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Different jobs\Transfer\Text OFF
Transfer	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Different jobs\Transfer\Text ON
Transition structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Trans6
Transition structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Trans8
Transition structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Trans1
Transition structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Trans2
Transition structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Trans3
Transition structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Trans9
Transition structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Trans7
Transition structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Trans5
Transition structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Trans10
Transition structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Trans4
Transition structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Trans12
Transition structure	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\ProcessSequence [FB1]\Trans11
TT/TI-517 sensor´s scaled value	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Scaled_TI517
TT/TI-518 sensor´s scaled value	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Main [OB1]\Scaled_TI518
TT-517	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_14\Text
TT-518	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screens\Root screen\Text field_15\Text
Unacknowledged alarms	HMI screen	ChemicalProcess\HMI_1 [KTP700 Basic PN]\Screen management\Global screen\Alarm window_Unacknowledged\Label
Usable output for futher use.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\FC_Scale [FC2]\ActualOutput
Usable output for futher use.	Block comment	ChemicalProcess\PLC_1 [CPU 1511-1 PN]\Program blocks\Sensors\Generic Blocks\SensorScaling [FB3]\ActualOutput
User administration	HMI runtime	ChemicalProcess\HMI_1 [KTP700 Basic PN]\User administration\User administration\Short-Name

Totally Integrated Automation Portal																																																																												
ChemicalProcess / Languages & resources Project graphics AlarmDisplay_KTP700_Basic_PN_TR <table><tr><th>Standard graphic</th><th>English (United States)</th></tr><tr><td></td><td></td></tr><tr><td colspan="2">▶ <i>Dithering mode</i></td></tr><tr><td>Same color</td><td>Same color</td></tr><tr><td colspan="2">▶ <i>Smoothing</i></td></tr><tr><td>Disabled</td><td>Disabled</td></tr></table> Down_Arrow <table><tr><th>Standard graphic</th><th>English (United States)</th></tr><tr><td></td><td></td></tr><tr><td colspan="2">▶ <i>Dithering mode</i></td></tr><tr><td>Same color</td><td>Same color</td></tr><tr><td colspan="2">▶ <i>Smoothing</i></td></tr><tr><td>Disabled</td><td>Disabled</td></tr></table> ExitRuntime_KTP700_Basic_PN_TR <table><tr><th>Standard graphic</th><th>English (United States)</th></tr><tr><td></td><td></td></tr><tr><td colspan="2">▶ <i>Dithering mode</i></td></tr><tr><td>Same color</td><td>Same color</td></tr><tr><td colspan="2">▶ <i>Smoothing</i></td></tr><tr><td>Disabled</td><td>Disabled</td></tr></table> Home <table><tr><th>Standard graphic</th><th>English (United States)</th></tr><tr><td></td><td></td></tr><tr><td colspan="2">▶ <i>Dithering mode</i></td></tr><tr><td>Same color</td><td>Same color</td></tr><tr><td colspan="2">▶ <i>Smoothing</i></td></tr><tr><td>Disabled</td><td>Disabled</td></tr></table> Left_Arrow <table><tr><th>Standard graphic</th><th>English (United States)</th></tr><tr><td></td><td></td></tr><tr><td colspan="2">▶ <i>Dithering mode</i></td></tr><tr><td>Same color</td><td>Same color</td></tr><tr><td colspan="2">▶ <i>Smoothing</i></td></tr><tr><td>Disabled</td><td>Disabled</td></tr></table> Logo of HMI_1 <table><tr><th>Standard graphic</th><th>English (United States)</th></tr><tr><td></td><td></td></tr><tr><td colspan="2">▶ <i>Dithering mode</i></td></tr><tr><td>Same color</td><td>Same color</td></tr><tr><td colspan="2">▶ <i>Smoothing</i></td></tr><tr><td>Disabled</td><td>Disabled</td></tr></table>			Standard graphic	English (United States)			▶ <i>Dithering mode</i>		Same color	Same color	▶ <i>Smoothing</i>		Disabled	Disabled	Standard graphic	English (United States)			▶ <i>Dithering mode</i>		Same color	Same color	▶ <i>Smoothing</i>		Disabled	Disabled	Standard graphic	English (United States)			▶ <i>Dithering mode</i>		Same color	Same color	▶ <i>Smoothing</i>		Disabled	Disabled	Standard graphic	English (United States)			▶ <i>Dithering mode</i>		Same color	Same color	▶ <i>Smoothing</i>		Disabled	Disabled	Standard graphic	English (United States)			▶ <i>Dithering mode</i>		Same color	Same color	▶ <i>Smoothing</i>		Disabled	Disabled	Standard graphic	English (United States)			▶ <i>Dithering mode</i>		Same color	Same color	▶ <i>Smoothing</i>		Disabled	Disabled		
Standard graphic	English (United States)																																																																											
																																																																												
▶ <i>Dithering mode</i>																																																																												
Same color	Same color																																																																											
▶ <i>Smoothing</i>																																																																												
Disabled	Disabled																																																																											
Standard graphic	English (United States)																																																																											
																																																																												
▶ <i>Dithering mode</i>																																																																												
Same color	Same color																																																																											
▶ <i>Smoothing</i>																																																																												
Disabled	Disabled																																																																											
Standard graphic	English (United States)																																																																											
																																																																												
▶ <i>Dithering mode</i>																																																																												
Same color	Same color																																																																											
▶ <i>Smoothing</i>																																																																												
Disabled	Disabled																																																																											
Standard graphic	English (United States)																																																																											
																																																																												
▶ <i>Dithering mode</i>																																																																												
Same color	Same color																																																																											
▶ <i>Smoothing</i>																																																																												
Disabled	Disabled																																																																											
Standard graphic	English (United States)																																																																											
																																																																												
▶ <i>Dithering mode</i>																																																																												
Same color	Same color																																																																											
▶ <i>Smoothing</i>																																																																												
Disabled	Disabled																																																																											
Standard graphic	English (United States)																																																																											
																																																																												
▶ <i>Dithering mode</i>																																																																												
Same color	Same color																																																																											
▶ <i>Smoothing</i>																																																																												
Disabled	Disabled																																																																											

Totally Integrated Automation Portal		
NavigateHome_KTP700_Basic_PN_TR		
Standard graphic	English (United States)	
		
▶ <i>Dithering mode</i>		
Same color	Same color	
▶ <i>Smoothing</i>		
Disabled	Disabled	
Navigates to Different jobs for KTP700 Basic+ PN 16.0.0.0		
Standard graphic	English (United States)	
		
▶ <i>Dithering mode</i>		
Same color	Same color	
▶ <i>Smoothing</i>		
Disabled	Disabled	
Navigates to Project information for KTP700 Basic+ PN 16.0.0.0		
Standard graphic	English (United States)	
		
▶ <i>Dithering mode</i>		
Same color	Same color	
▶ <i>Smoothing</i>		
Disabled	Disabled	
Navigates to SIMATIC PLC system diagnostics for KTP700 Basic+ PN 16.0.0.0		
Standard graphic	English (United States)	
		
▶ <i>Dithering mode</i>		
Same color	Same color	
▶ <i>Smoothing</i>		
Disabled	Disabled	
Navigates to System information for KTP700 Basic+ PN 16.0.0.0		
Standard graphic	English (United States)	
		
▶ <i>Dithering mode</i>		
Same color	Same color	
▶ <i>Smoothing</i>		
Disabled	Disabled	
Navigates to System screens for KTP700 Basic+ PN 16.0.0.0		
Standard graphic	English (United States)	
		
▶ <i>Dithering mode</i>		
Same color	Same color	
▶ <i>Smoothing</i>		
Disabled	Disabled	
Navigates to User administration for KTP700 Basic+ PN 16.0.0.0		
Standard graphic	English (United States)	
		
▶ <i>Dithering mode</i>		
Same color	Same color	
▶ <i>Smoothing</i>		
Disabled	Disabled	
Right_Arrow		
Standard graphic	English (United States)	
		
▶ <i>Dithering mode</i>		
Same color	Same color	

